If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

4603 A-Line Dress with Wide Asymmetrical Skirt

Recommendations on fabric: natural/mixed fabric suitable for dresses.



You will also need: fusible interfacing; 1 button.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm.

Main fabric:
1. Back – cut 1 on fold
2. Front – cut 1 on fold
3. Back facing – cut 1
4. Front facing – cut 1

Fusible interfacing:
1. Back facing – cut 1
2. Front facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to the facings.

2. Sew the darts on the front and press the dart excess upward.

3. Sew the shoulder seams and press the seam allowances open. Sew the side seams. Serge the seam allowances and press them toward the back.

4. Sew the shoulder and side seams of the facings. Press the seam allowances open. Serge the lower edge of the facing. Pin the facing to the dress, right sides together, and sew along the neckline.

5. Cut a strip of bias tape measuring 2.5 cm wide and 5 cm long for the button loop. Fold the tape in half lengthwise, right sides together, and stitch 0.3 cm from the fold. Trim the seam allowance, turn the tape right side out, and shape it into a cord. Adjust the length to form the button loop.

6. To make the button closure, cut through the center back facing and back from the neckline to the marked point. Insert the button loop into the upper corner beneath the neckline stitching. Stitch close to both sides of the opening, securing the ends of the button loop at the same time. Bring the stitching to a point at the lower end of the opening and reinforce the stitches. Trim the neckline seam allowance. Turn the facing to the wrong side and press. Finish the armhole edges with the facing in two stages – first the front armholes, then the back armholes.

7. Serge the lower edge of the dress, press the hem allowance to the wrong side, and topstitch. Sew on the button.

Congratulations – your dress are finished! :)