If the pattern has a double line around it, the seam allowances are included.


Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 5130 Double-Layer Dress with Short Sleeves



Recommendations on fabric: fabric suitable for dress, e.g. cotton, viscose, artificial silk.

You will also need: fusing, 4 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm, for hem – 2 cm.

<u>Main fabric:</u>
1. back upper part – 1 piece
2. back middle lower part – 2 pieces
3. back side lower part – 2 pieces
4. back side part – 2 pieces
5. front side lower part – 2 pieces
6. front middle lower part (flying) – 2 pieces
7. front side upper part 1 – 2 pieces
8. upper flying part – 2 pieces
9. sleeve – 2 pieces

10. back neckline facing – 1 piece
11. facing of flying detail – 2 pieces

Decorative fabric:

1. front side lower part – 2 pieces
2. front middle lower part – 1 piece
3. front side upper part – 2 pieces
4. front upper part – 2 pieces
5. front part facing – 2 pieces
6. shoulder pad – 2 pieces

INSTRUCTIONS:

1. Sew the back darts and press. Sew the upper and lower back sections together. Sew the back princess seams up to the marked notches.

2. Finish the upper edge of the loose overlay with its facing, right sides together. Turn the facing to the wrong side and press. Sew the upper and lower front overlay sections together. Sew the front princess seams up to the marked notches. Sew the princess seams of the upper front bodice pieces. Sew the shoulder seams, joining the front and back bodice pieces.

3. Apply fusible interfacing to the wrong side of the back neckline facings and front facings. Sew the back neckline facing pieces together, then attach them to the front facings. Press the seam allowances. Serge the inner edges of the neckline and front facings. Pin the facings to the dress, right sides together, and sew along the neckline and front opening edges. Turn the facings to the wrong side, shape the edges, and topstitch 0.5 cm from the finished edges. Press.

4. Sew the seams of the lower front sections. Attach the lower front sections to the upper front bodice.

5. Press the lower sleeve hem allowances to the wrong side and secure the hems with hand stitches. Set the sleeves into the armholes, aligning the front armhole edges with the corresponding edges of the front overlays. Match the pattern notches and distribute the gathers evenly along the sleeve caps. Serge the armhole seam allowances.

6. Fold the dress hem allowance to the wrong side, press, and stitch the hem in place.

7. Make the buttonholes at the marked positions and sew on the buttons.

Congratulations – your dress are finished! :)