

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2047 Jacket with Loose Decorative Panel and Short Sleeves

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: decorative fabric; fusible interfacing; lining; thin shoulder pads; 1 snap-fastener.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment 3 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front – cut 2
5. Front fly piece – cut 2
6. Center front facing – cut 2

7. Back neck facing – cut 1
8. Sleeve – cut 2

Decorative fabric:

1. Cuff – cut 2
2. Front fly piece – cut 2

Lining is cut using the pattern blocks for self fabric, except for the width of back neckline facing.

Lining:

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front lining – cut 2
5. Sleeve - cut 2
6. Cuff – cut 2

Fusible interfacing: center front, center front facing, back neck facing.

INSTRUCTIONS:

1. Apply fusible interfacing. Cut a strip of interfacing and apply it along the edge of the back neckline.
2. Pin the front fly pieces together with right sides facing and sew the outer and lower edges. Trim the corners and turn the piece right side out. Press. Pin the fly piece to the center front and baste along the princess seam edge and shoulder edge.
3. Sew the princess seam on the front. Press the seam toward the side.
4. Sew the side back to the center back and press the seam open. Sew the center back seam and press it open.
5. Sew the shoulder seams of the jacket and press them open. Sew the side seams of the jacket and press them open.
6. Sew the sleeve seam and press the seam allowances open. Sew the cuff into a ring and press the seam open. Fold the cuff in half lengthwise and sew it to the lower edge of the sleeve.

7. Sew the sleeves into the armholes, matching notches and easing along the upper sleeve cap. Sew in the shoulder pads.
8. Sew and press open the shoulder seams of the back neckline facing and button stand. Sew the lining pieces together in the same way as the main fabric pieces, leaving an opening in the left sleeve's elbow seam. Sew the lining to the facing and button stands.
9. Pin the jacket and lining together with right sides facing, matching all outer edges. Sew the lining to the center front facing and neckline. Sew the lining to the jacket hem and to the sleeve hems. Turn the jacket right side out through the opening. Sew the opening closed.
10. Slipstitch the fly piece in place from the wrong side.
11. Install a snap fastener on the front.

Congratulations, your jacket is ready! :)