

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2049 Cropped Women's Jacket with Wide Waistband

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; lining; thin shoulder pads; 3 buttons; 1 inner button.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance on lower edge of sleeve 3 cm.

Main fabric:

1. Back – cut 2
2. Front – cut 2
3. Belt – cut 2 on fold
4. Center front facing – cut 2
5. Back neck facing – cut 1
6. Upper sleeve – cut 2

7. Lower sleeve – cut 2

Lining is cut using pattern blocks for main fabric, except for the width of back neckline facing and buttonstands.

Lining:

1. Back – cut 2
2. Front – cut 2
4. Upper sleeve – cut 2
5. Lower sleeve – cut 2

Fusible interfacing: front, center front facing, back neck facing, belt.

INSTRUCTIONS:

1. Apply fusible interfacing. Apply an additional strip of fusible interfacing along the back neckline and the sleeve hem.
2. Sew a gathering stitch along the lower edge of the front between the markings and gather the fullness.
3. Sew the darts on the back and press the bulk toward the center. Sew the center back seam and press it open.
4. Sew the shoulder and side seams of the jacket and press the seams open.
5. Sew the elbow seam on the sleeve. Press the seam open. Press the sleeve hem. Sew and press open the front sleeve seam.
6. Sew the sleeves into the armholes, matching notches and easing the fullness along the upper sleeve cap. Insert shoulder pads.
7. Sew and press open the shoulder seams of the back neckline facing and button stand. Sew the lining pieces together in the same way as the main fabric pieces. Sew the lining to the facing and button stands.
8. Sew the lining to the sleeve hems. Pin the jacket and lining together with right sides facing, aligning all outer edges. Sew the lining to the center front facing and neckline. Turn the jacket right side out.
9. Pin the belt pieces together with right sides facing and sew along the lower edge and

center front edge. Trim the corners and turn right side out. Sew the outer belt to the lower edge of the jacket and press the seam allowance downward. Turn under the seam allowance of the inner waistband and stitch in the ditch.

10. Make buttonholes and sew on the buttons.

Congratulations, your jacket is ready! :)