

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2061 Stretch Blouson with Decorative Bow

Recommendations on fabric: natural/mixed knit fabric of small/medium stretchiness.

You will also need: dress zipper, knit fusible interfacing; decorative bow.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: seam allowance for hem of garment and hem of sleeve – 2 cm, center edge of lower front – 2 cm, other seams – 1 cm.

Main fabric:

1. Front – cut 1 on fold
2. Back – cut 2
3. Lower front – cut 2
4. Lower back – cut 2
5. Front neck facing – cut 1
6. Back neck facing – cut 2



INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. Apply fusible interfacing to the facings.
2. Sew front darts. Press the bulk upward.
3. Sew upper backs to lower backs, serge the seams, and press upward. Serge the center back edges separately. Sew the center back seam from the notch for the zipper to the bottom; press the seam open. Sew in the zipper.
4. Serge the center edges of the lower front. Turn the seam allowances to the inside and topstitch 1.5 cm from the edge. Pin the right part over the left part and baste together along the upper edge. Sew the lower front to the upper front; serge and press upward.
5. Sew shoulder and side seams; press the seams toward the back and serge.
6. Sew the shoulder seams of the neck facings; press the seams open. Serge the outer edge. Pin the facing to the garment, right sides together. Sew the neckline. Clip the seam allowances along the curves. Fold the facing to the wrong side, straighten, and press. Slipstitch the facing to the shell along the shoulder seams. Slipstitch the facing to the zipper tape.
7. Sew the sleeve seam; serge and press toward the back. Sew the sleeves into the armholes; serge and press.
8. Serge the hem of the garment and the lower edge of the sleeves; press to the wrong side and topstitch.
9. Sew the decorative bow.

Congratulations, your blouson is ready! :)