

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2075 Fitted Dress with Patch Pockets

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; hidden closure-zipper; 7 buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment – 3 cm.

Main fabric:

1. Upper back – cut 2
2. Upper center front – cut 2
3. Upper side front – cut 2
4. Collar – cut 2
5. Lower back - cut 2
6. Lower front – cut 1 on fold

7. Upper sleeve – cut 2
8. Lower sleeve – cut 2
9. Back neck facing – cut 1
10. Center front facing – cut 2
11. Pocket – cut 2
12. Flap – cut 4
13. Cuff – cut 2

Fusible interfacing:

1. Center front – cut 2
2. Center front facing – cut 2
3. Collar – cut 1
4. Back neck facing – cut 1
5. Cuff – cut 2
6. Flap – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing. Also apply fusible interfacing to the lower back near the slit.
2. Sew darts on the upper back and lower back; press the bulk toward the center. Sew the upper back to the lower back; serge and press downward. Serge the center back edges separately. Sew the center back seam from the top to the zipper mark, and from the second zipper mark to the slit marking. Press the seam open. Sew in the zipper. Sew a fastening stitch along the slit, 0.2 cm from the edge.
3. Sew the side fronts to the front; serge the seams and press toward the center. Sew darts on the lower front; press the bulk toward the center.
4. Sew the shoulder seams of the dress; serge and press open.
5. Pin the upper collar to the lower collar and sew the corners and collar fall. Start and stop stitching exactly at the marked seam line between the collar and the garment. Trim the corners and clip into the seam allowance near the notch. Turn the collar right side out, straighten, and press.
6. Sew the shoulder edges of the center front facings and the back neckline facing; press the seam open. Serge the outer edge.
7. Place the center front facing onto the front, right sides together. Pin and sew along

the center front and lapel. Sew upward to the notch marking the end of the collar seam. Trim the corners. Topstitch the seam allowance along the center front edge—onto the center front facing along the closure, and onto the front along the part that is folded away. Place the stitch line 0.2 cm from the seam. Turn the buttonstands (center front edges) right side out and straighten the seams.

8. Sew the lower collar into the neckline of the shell. Sew the upper collar into the neckline of the back neckline facing and center front facing. Press the collar seam allowances open and baste them together close to the seam.
9. Pin the flaps together, right sides facing, and sew along the side and lower edges. Trim the seam allowances, turn the flap right side out, and press. Serge the pocket around all edges. Turn under the upper edge and topstitch. Fold the seam allowances of the pocket to the wrong side and press. Pin the pocket onto the lower front and topstitch. Sew the flap to the front along the upper pocket marking line (the finished edge should face the neckline).
10. Place the right front over the left front, aligning the center lines, and baste together along the lower edge. Sew the lower front to the upper front; serge and press downward.
11. Sew the side seams; serge and press toward the back.
12. Sew and press the elbow seam open; serge. Sew and press open the front sleeve seam; serge. Sew the sleeve into the armhole; serge the seam allowances.
13. Serge the lower edge of the garment. Fold the seam allowances to the wrong side and topstitch or hem as desired.
14. Pin the cuffs together, right sides facing, and sew one long and one short side. Start and stop stitching exactly at the marked cuff attachment line. Trim the corners, turn the cuff right side out, and press. Sew the outer side of the cuff to the sleeve, matching the notch with the front seam. Fold under the seam allowance of the inner side and stitch-in-the-ditch along the connecting seam. Fold the cuff upward.
15. Make buttonholes on the front and on the flaps. Sew on the buttons.

Congratulations, your dress is ready! :)