

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2085 Jacket with Angled Edge

Recommendations on fabric: natural/mixed suiting fabric.

You will also need: fusible interfacing; lining; shoulder pads, sleeve heads.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance along hem of jacket and hem of sleeve – 3 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Sleeve – cut 2
6. Back neck facing – cut 1

7. Center front facing – cut 2

Lining:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Sleeve – cut 2

Fusible interfacing:

1. Center front – cut 2
2. Back neck facing – cut 1
3. Center front facing – cut 2

Attention: front and back from lining are cut using the pattern blocks for self fabric, with the exception for the areas of center front facing and back neckline facing.

INSTRUCTIONS:

1. Apply fusible interfacing. Also apply fusible interfacing to the seam allowances along the hem of the garment and the hem of the sleeves.
2. Sew the center back seam; press the seam open. Sew the side backs to the center back; press toward the center.
3. Sew the side fronts to the front; press toward the center.
4. Sew and press open the side edges of the jacket.
5. Sew the center edge of the one-piece collar; press the seam open. Sew the shoulder seams. Sew the collar into the back neckline, clipping into the seam allowance near the corner. Clip the seam allowances and press open.
6. Sew the center edge of the one-piece collar to the center front facing; press the seam open. Sew the shoulder seams of the back neckline facing and buttonstand. Sew the collar into the back neckline, clipping into the seam allowance near the corner. Clip the seam allowances and press open. Pin the facings and center front facings to the front, right sides together, and sew the buttonstand and neckline. Trim the corners and clip the curves. Fold the center front facings (buttonstands) to the right side, straighten the seams, and press. Slipstitch the seam allowances together along the collar seams.

7. Sew and press open the sleeve seams. Sew the sleeves into the armholes, matching notches and adjusting ease at the sleeve cap. Sew in shoulder pads and sleeve heads.
8. Sew the seams on the lining and insert the sleeves, leaving an opening in the left front sleeve seam. Sew the lining to the inner edges of the center front facings (buttonstands) and to the facing. Press the lower edge of the garment to the wrong side. Sew the lining to the hem of the garment and the hem of the sleeves. Turn the jacket right side out through the opening. Sew the opening closed.

Congratulations, your jacket is ready! :)