

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2089 Denim Jacket with Drawstring Waist

Recommendations on fabric: natural/mixed jeans fabrics, denim.

You will also need: fusible interfacing; lining; 3 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve – 2.5 cm. Seam allowance along short edges of casing – 2 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Back yoke – cut 1
4. Center front – cut 2
5. Side front – cut 2
6. Front yoke – cut 2

7. Lower collar - cut 1
8. Upper collar – cut 1
9. Center front facing – cut 2
10. Back neck facing – cut 1
11. Sleeve – cut 2
12. Casing for drawstring – cut 1
13. Flap – cut 4
14. Pocket frame – cut 2
15. Belt – cut 1

Lining:

1. Smaller pocket bag – cut 2
2. Bigger pocket bag – cut 2

Fusible interfacing:

1. Center front facing – cut 2
2. Back neck facing – cut 1
3. Upper collar – cut 1
4. Flap – cut 2
5. Pocket frame – cut 2
6. Belt – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing. Apply fusing along the front lapel fold; the width should be 1 cm.
2. Sew the center back seam, serge, and press toward the left. Sew the back yoke to the back; serge and press toward the yoke. Sew a decorative stitch 0.5 cm from the seam. Sew the side backs to the center back; serge the seams and press toward the center. Sew a decorative stitch 0.5 cm from the seam.
3. Sew the yoke to the front; serge and press toward the yoke. Sew a decorative stitch 0.5 cm from the seam. Sew the side front to the center front; serge the seams and press toward the center. Sew a decorative stitch 0.5 cm from the seam.
4. Sew the flaps together in pairs, right sides facing, along the sides and lower edges. Trim seam allowances, clip curves, turn right side out, and press. Mark the pocket placement with parallel lines. Fold the pocket frame in half, wrong sides together, and press. Mark additional stitching lines on the pocket frame and flap for alignment. Sew the larger pocket bag to the pocket flap. Sew the pocket frame and

flap to the front. Slash the front along the marked line on the pattern. Snip diagonally toward the end of the stitching, 1–1.5 cm from the pocket opening. Turn the pocket frame and flap to the wrong side through the opening and straighten the edges. Secure the corners of the pocket by stitching a double line from the wrong side at the corners. Sew the smaller pocket bag into the seam of the pocket frame. Sew the edges of the pocket bags together and serge.

5. Sew the shoulder and side seams; serge and press toward the back.
6. Turn under the short edges of the casing twice by 1 cm and topstitch. Turn under the seam allowances along the long edges and topstitch the casing onto the jacket along the marked lines.
7. Pin the upper collar to the lower collar and sew the corners and collar fall. Start and stop sewing exactly at the marked seam line between the collar and garment. Clip curves and into the seam allowance near the notch. Turn the collar right side out, straighten, and press.
8. Sew and press open the shoulder seams of the back neckline facing and buttonstand.
9. Place the center front facing onto the front, right sides together; pin and sew along the center front edge up to the notch marking the end of the collar seam.
10. Sew the lower collar into the neckline of the shell; sew the upper collar into the neckline of the back facing and center front facing. Press the collar seam allowances open and slipstitch them together close to the seam.
11. Sew the sleeve seams; press toward the back. Sew the sleeves into the armholes, matching notches and adjusting the ease along the upper side of the sleeve cap.
12. Serge the sleeve and jacket hems, turn to the inside, and topstitch. Sew a decorative stitch 0.5 cm from the edge along the center front and collar.
13. Make buttonholes and sew on the buttons.
14. Fold the belt in half lengthwise, right sides together, and sew around all edges, leaving an opening for turning. Trim the corners, turn the piece right side out, and press. Sew the opening closed. Thread the belt through the casing.

Congratulations, your jacket is ready! :)