

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2114 Denim Dress with Puff Sleeves

Recommendations on fabric: thick natural/mixed fabric suitable for dresses. Denim.

You will also need: fusible interfacing, 7 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: seam allowance for hem of garment – 2 cm, other seams 1 cm.

Main fabric:

1. Upper back – cut 2
2. Center back waistband – cut 1
3. Side back waistband – cut 2
4. Lower back – cut 2
5. Upper front – cut 2
6. Center front waistband – cut 2
7. Side front waistband – cut 2



8. Lower front – cut 2
9. Sleeve – cut 2
10. Cuff – cut 2
11. Collar – cut 2
12. Center front facing – cut 2
13. Back neck facing – cut 1

Fusible interfacing:

1. Collar – cut 1
2. Center front facing – cut 2
3. Back neck facing – cut 1
4. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on the upper backs, pressing bulk towards the center. Sew the center seam on the upper back, press towards the left, and serge.
3. Sew the center back waistband to the side back waistband, press towards the center, and serge. Sew a decorative stitch 0.2 cm from the seam. Sew the back belt to the upper part, press seam allowances towards the belt, and serge.
4. Sew a gathering stitch along the lower edge of the upper front and gather fullness.
5. Sew the center front waistband to the side front waistband, press towards the center, and serge. Sew a decorative stitch 0.2 cm from the seam. Sew the front belt to the upper piece, press seam allowances towards the belt, and serge. Sew a decorative stitch 0.2 cm from the seam.
6. Pin collars together, right sides facing, and sew collar ends and collar fall, starting and stopping exactly at the marked seam line between the collar and garment. Trim corners and clip into the seam allowance near the notch. Turn the collar right side out, straighten, and press. Sew a decorative stitch 0.2 cm from the edge.
7. Sew shoulder edges of the garment, press seams towards the back, and serge. Sew side seams of the back neckline facing and buttonstands, press seams open, and serge the outer edge.
8. Place the center front facing onto the front, right sides together, pin, and sew along

the center front edge up to the notch marking the end of the collar seam. Trim corners. Turn buttonstands (center front edges) right side out and straighten seams.

9. Sew the lower collar into the neckline of the shell, sew the upper collar into the neckline of the back facing and center front facing. Clip into the seam allowances of the collar, press open, and slipstitch close to the seam.
10. Make buttonholes on the right front. Place the right upper front over the left upper front and baste together along the lower edge.
11. Sew the center seam on the lower back, press towards the left, and serge. Sew a gathering stitch along the upper edge of the lower back and gather fullness. Sew the upper back to the lower back, press towards the top, and serge. Sew a decorative stitch 0.2 cm from the seam.
12. Sew the center seam of the lower front, press towards the left, and serge. Sew a gathering stitch along the upper edge of the lower front and gather fullness. Sew the upper front to the lower front, press towards the top, and serge. Sew a decorative stitch 0.2 cm from the seam.
13. Sew side seams, press towards the back, and serge.
14. Sew sleeve edges separately. Sew a gathering stitch along the lower edge and gather fullness. Make and baste pleats along the sleeve cap. Sew the sleeve seam from the armhole to the slit mark, press seams open. Topstitch the slit 0.1 cm from the fold. Sew sleeves into armholes, serge, and press.
15. Fold the cuff in half lengthwise, right sides together, and sew side seams. Turn the cuff right side out and press. Sew the outer side of the cuff to the sleeve, fold inside the seam allowance of the inner cuff, and stitch in the ditch along the seam of the outer cuff.
16. Serge the lower edge of the garment, press to the wrong side, and topstitch.
17. Make buttonholes on the cuffs, sew on buttons, and sew buttons on the left front.

Congratulations – your dress are finished! :)