

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2205 Top with Zipper and Stand Collar

Recommendations on fabric: well draping natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing, zipper.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm.

Main fabric:

1. Front – cut 1 on fold
2. Back – cut 2
3. Stand collar – cut 2

Fusible interfacing:

1. Stand collar – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing to the stand collar.



2. Sew the center back seam, serge, and press to the left.
3. Sew a gathering stitch along the upper edge of the front from the mark to the neckline and gather fullness. Sew the one-piece yoke to the front, serge, and press towards the yoke.
4. Cut the front at the center front neckline to the mark. Clip into the seam allowance on the front, leaving 1 mm to the stitch line. Clip into the seam allowance near the mark. Serge the shaped neckline edges up to the notch. Pin the zipper to the right side of the front, right side down. Sew the zipper along the two longer edges, then fold it to the wrong side. Secure the corner from the wrong side. Sew a fixing stitch along the zipper, 0.5 cm from the teeth.
5. Pin the stand collar pieces right sides together and sew the short edges and upper edge, starting and stopping exactly at the marked neckline seam line. Clip seam allowances and trim corners.
6. Cut (or prepare) bias tape 4 cm wide and as long as the armhole plus 4 cm. Fold the bias tape in half lengthwise, right side out, and press. Pin the bias tape to the armhole edge from the right side, leaving loose ends, and stitch. Fold the bias tape to the wrong side, clip seam allowances, and topstitch along the seam. Press.
7. Serge the lower edge of the garment, press to the wrong side, and topstitch.
8. Sew side seams, press towards the back, and serge.

Congratulations – your top are finished! :)