

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2215 Blouse with 3/4 Sleeves

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: 1 button.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: seam allowance for hem of garment and hem of sleeve – 1.5 cm, other seams 1 cm.

Main fabric:

1. Back yoke – cut 2
2. Side back – cut 2
3. Front yoke – cut 1
4. Side front – cut 2
5. Sleeve – cut 2

Main fabric 1:

1. Center back – cut 1 on fold
2. Center front – cut 1 on fold

INSTRUCTIONS:

1. Serge the center edges of the back yokes separately and press to the wrong side. Sew a fixing stitch along the slit edge, 0.1 cm from the edge.
2. Sew side backs to the center back, serge, and press towards the center. Sew back yokes to the back, press seam allowances towards the yoke, and serge.
3. Sew side fronts to the center front, press towards the center, and serge. Sew the front yoke to the front, serge, and press towards the yoke.
4. Sew side and shoulder seams, press towards the back, and serge.
5. Cut (or prepare) bias tape 2.5 cm wide and 5 cm long for the loop buttonhole. Fold the tape in half lengthwise, right sides together, and stitch 0.3 cm from the fold. Trim seam allowances close to the seam, turn the tape right side out, and form a narrow rolled hem. Adjust the loop length.
6. Cut (or prepare) bias tape 4 cm wide and as long as the neckline plus 4 cm. Fold the bias tape in half lengthwise, right side out, and press. Pin the bias tape to the neckline from the right side, leaving loose ends, and stitch. Fold the bias tape to the wrong side, clip seam allowances, and topstitch onto the garment along the seam. Press. Sew the button loop to the left back yoke.
7. Sew the sleeve seam, serge, and press towards the back. Insert sleeves into armholes, serge, and press.
8. Serge the hem of the garment and the sleeve hems, press to the wrong side, and topstitch.
9. Sew a button to the right back yoke.

Congratulations – your blouse are finished! :)