

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2224 Sailor Jacket for Women

Recommendations on fabric: natural/mixed fabric suitable for coats.

You will also need: lining; fusible interfacing; 6 buttons; 1 inner button; shoulder pads.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment – 3 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Upper collar – cut 1
6. Lower collar – cut 1
7. Upper sleeve – cut 2
8. Lower sleeve – cut 2
9. Cuff – cut 2
10. Back neck facing – cut 1
11. Center front facing – cut 2

12. Off-set welt – cut 2

Lining:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Upper sleeve – cut 2
6. Lower sleeve – cut 2
7. Pocket bag – cut 4

Attention: lining for back and front is cut using pattern blocks for main fabric except for back neckline facing and buttonstands accordingly.

Fusible interfacing:

1. Center front – cut 2
2. Center front facing – cut 2
3. Upper collar – cut 1
4. Back neck facing – cut 1
5. Off-set welt – cut 2
6. Cuff – cut 2

Also apply fusible interfacing to sewing allowances of back armhole, lower edge of garment and seam allowance along the pocket opening.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on the back, pressing bulk towards the center. Sew side backs to center back, press seams open. Sew center back seam, press open.
3. Sew darts on the center front, pressing bulk upwards. Sew side fronts to front, press seams open.
4. Mark the pocket position on the front with two parallel stitch lines. Fold the off-set welt in half lengthwise, right sides together, and sew side edges. Turn the welt right side out and press. Sew a decorative stitch around the contour, 1 cm from the edge. Mark the line on the welt that indicates its finished width. Topstitch the pocket bag to the inner side of the welt, aligning the centers. Place the welt on the right side of the front, right side down, along the marking line. Stitch the welt in place. Sew the

second pocket bag to the other pocket marking line. Slash the pocket opening between the marked lines, cutting diagonally into the corners. Turn the pocket pieces to the wrong side. Straighten seam allowances and press. Sew together the edges of the pocket bags, securing the corners. Topstitch the welt to the front along the shorter edges.

5. Sew the shoulder and side seams of the garment, press seams open.
6. Pin the upper collar to the lower collar and sew corners and fall. Start and stop sewing exactly at the marked collar–garment seam line. Clip curves and into the seam allowance near the notch. Turn the collar right side out, straighten, and press.
7. Sew the shoulder edges of the center front facings and back neckline facing, press seams open.
8. Place the center front facing onto the front, right sides together, pin, and sew along the center front and lapel. Sew upwards to the notch marking the end of the collar seam. Trim corners. Topstitch the seam allowance along the center front edge to the center front facing along the closure, and to the front along the folded section. Place stitching 0.2 cm from the seam. Turn buttonstands (center front edges) right side out, straighten seams.
9. Sew the lower collar to the neckline of the shell. Sew the upper collar to the neckline facings of the back and center front. Press collar seam allowances open and baste them together close to the seam.
10. Sew and press open the front sleeve seam. Fold the cuff in half lengthwise, right side out, and press. Unfold and sew the outer side of the cuff to the lower edge of the sleeve, pressing seam towards the cuff. Sew the elbow seam, attaching the cuff at the same time. Insert sleeve into the armhole. Attach shoulder pads.
11. Sew lining seams, leaving an opening in the left side seam for turning. Sew lining to buttonstands and facings. Sew the lower corners of the center front facings, trim corners. Mark and press the lower edge of the garment to the wrong side. Sew lining to the lower edge of the garment. Attach sleeve linings to inner cuffs. Turn the garment right side out through the opening and sew the opening closed.
12. Make buttonholes on the right front. Sew buttons on the left front. Sew decorative buttons on the right front. Make an inner buttonhole on the left front and attach the hidden button.
Congratulations – your jacket are finished! :)