

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 2284 Denim Jacket with Button Closure

Recommendations on fabric: natural/mixed jeans fabrics.

You will also need: fusible interfacing; 7 buttons.

### CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm.

### Main fabric:

1. Upper center back – cut 1 on fold
2. Lower center back – cut 1
3. Upper side back – cut 2
4. Lower side back – cut 2
5. Upper center front – cut 2
6. Upper side front – cut 2
7. Lower side front – cut 2
8. Lower center front – cut 2
9. Stand collar - cut 2



10. Placket – cut 2
11. Upper sleeve – cut 2
12. Lower sleeve – cut 2
13. Cuff – cut 2

Fusible interfacing:

1. Stand collar – cut 1
2. Placket – cut 2
3. Cuff - cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the center upper back to the center lower back, press the seam upward, serge, and topstitch decoratively 0.5 cm from the seam. Sew the side upper back to the side lower back, press upward, serge, and topstitch decoratively 0.5 cm from the seam. Sew the side back pieces to the center back, press toward the side seam, serge, and topstitch decoratively 0.5 cm from the seam.
3. Sew the center lower front to the center upper front, press the seam upward, serge, and topstitch decoratively 0.5 cm from the seam. Sew the side upper front to the side lower front, press upward, serge, and topstitch decoratively 0.5 cm from the seam. Sew the side front pieces to the center front, press toward the side seam, serge, and topstitch decoratively 0.5 cm from the seam.
4. Sew the shoulder and side seams, press the seams toward the back, and serge.
5. Cut a bias tape from the main fabric, 4 cm wide and equal in length to the lower edge. Apply fusible interfacing to the tape. Press the upper edge to the wrong side by 1 cm. Pin the tape to the lower edge of the garment, right sides together, and sew. Clip the seam allowances, fold the tape to the wrong side, and topstitch along the upper fold.
6. Fold the plackets in half lengthwise with right sides together and sew the upper and lower corners, starting and stopping exactly at the marked placket seam line. Turn the plackets right side out, shape, and press. Sew the outer edge of each placket to the front and press the seam allowances toward the placket. Fold the inner seam allowance to the wrong side, press, and stitch in the ditch.
7. Pin the stand collar pieces right sides together and sew the outer edge, starting and stopping exactly at the marked seam line between the stand collar and the garment. Clip the seam allowances. Turn the stand collar right side out, shape, and press. Sew the outer stand collar to the neckline and press the seam allowances toward the stand collar. Fold the inner seam allowance to the wrong side, press, and stitch in the ditch.
8. Sew the elbow edges of the sleeves separately. Sew the sleeve elbow seam from the

cap to the marking and clip into the seam allowance near the notch. Press the seam allowance from the sleeve cap to the marking and topstitch decoratively 0.5 cm from the seam. Press the seam allowances open from the marking down to the hem and topstitch decoratively 0.1 cm from the edges. Sew and press open the front sleeve seam. Sew the sleeves into the armholes, matching the notches.

9. Fold the cuffs in half lengthwise with right sides together and sew the short ends, starting and stopping exactly at the marked cuff seam line. Turn the cuffs right side out, shape, and press. Sew the outer edge of each cuff to the lower edge of the sleeve and press toward the cuff. Fold the inner seam allowance to the wrong side, press, and stitch in the ditch.
10. Make buttonholes on the right front and sew the buttons on the left front. Make buttonholes and sew buttons on the cuffs.

Congratulations – your jacket are finished! :)