

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2427 Blouse with collar and gathers

Recommendations on fabric: natural/mixed fabrics suitable for blouses approx. 1.5 meters (size 32-40), approx. 2 meters (size 42-54) with a fabric width of 150 cm.

You will also need: fusible interfacing, 5 buttons.



CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: Seam allowance for hem of garment – 2 cm, seam allowance for hem of sleeve – 1.5 cm, other seams – 1 cm.

Main fabric:

1. Back yoke – 1 piece
2. Back – 1 piece on fold
3. Front – 2 pieces
4. Front yoke – 2 pieces
5. Sleeve – 2 pieces
6. Neckline facing – 1 piece

Fusible interfacing:

1. Neckline facing – 1 piece

INSTRUCTIONS:

1. Apply fusible interfacing to facing.
2. Sew back yoke to yoke. Serge and press towards the top.
3. Serge the center front edges separately. Sew the center edges on front, press seam apart.
4. Sew a gathering stitch along the upper edge of front and gather fullness. Sew front yoke to front. Press towards top and serge.
5. Sew the side and shoulder seams. Serge seams and press towards back.
6. Sew collar seam. Press seam apart. Sew collar into front neckline and into back neckline, slashing front in the corner. Press towards collar.
7. Sew the edge of front neckline facing. Press seam apart. Serge the outer edge. Pin facing onto garment, right sides together and sew neckline, slashing into seam allowance in the lower corner of neckline.
8. Sew sleeve seam, serge and press towards back. Sew sleeves into armholes, serge and press.
9. Serge the hem of garment and hem of sleeve, turn inside and topstitch.
10. Sew on buttons onto front according to markings.

Congratulations, your blouse is ready! :)