

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2544 Bluse med polo lukning og kimonoærmer

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing, 2 buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: Seam allowance for hem of garment – 2 cm, seam allowance for hem of sleeve – 1.5 cm; other seams – 1 cm.

Main fabric:

1. Back - cut 1 on fold
2. Front - cut 1 on fold
3. Front placket – cut 4
4. Back neck facing – cut 2

Fusible interfacing:

1. Front placket – cut 2
2. Back neck facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the outer back neckline facing to back neckline, press towards facing.
3. Pin front plackets together pairwise right sides together and sew outer edge. Clip into curves, turn pieces right side out, straighten and press.
4. Sew plackets to front along longer edge, leaving the distance of 1 cm away from hem. Clip into seam allowance on front, leaving 1 mm to the stitch line. Make pleat on front, placing right placket over left placket. Sew together ends of plackets, folding away the front and fixing the lower edge. Serge.
5. Serge the outer edge of the inner back neckline facing. Pin neckline facing onto Back and sew neckline exactly up to the marked line of shoulder seam. Clip seam allowances, fold facing onto wrong side and press.
6. Sew shoulder seams, inserting the front between the inner back neckline facing and the outer back neckline facing, press seams towards back and serge.
7. Sew side seams, press seams towards back and serge.
8. Serge hem of garment and hem of sleeve, press onto wrong side and topstitch.
9. Sew on buttons on plackets, fixing them together.

Congratulations, your blouse is ready! :)