

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 2586 Jacket with contrast trim

Recommendations on fabric: natural/mixed knit fabric of small stretchiness in contrasting colors.

You will also need: fusible interfacing, shoulder pads, 1 button.



### CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve - 3 cm.

### Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front right – cut 1
5. Center front left – cut 1
6. Sleeve – cut 2
7. Center front facing left – cut 1
8. Back neck facing – cut 1

Main fabric 1:

1. Front decoration – cut 2

Fusible interfacing:

1. Center front facing left – cut 1
2. Back neck facing – cut 1
3. Front decoration – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew side backs to center back, press towards center, serge. Sew the center back seam, press towards left, serge.
3. Sew front darts, press bulk towards top. Sew side front to front, press towards center, serge.
4. Pin decorative pieces together, right sides together and sew center front edge and lower edge. Trim away corners, turn the piece right side out, press. Sew the decorative piece to the right front, press the seam allowances towards the main piece and serge.
5. Serge outer edge of center front facing. Pin the center front facing to the left front and sew the center front edge and lower edge. Trim away corners, turn the piece right side out, press.
6. Serge the outer edge of the back neckline facing. Pin neckline facing onto Back and sew neckline exactly up to the marked line of shoulder seam. Clip seam allowances, fold facing onto wrong side and press.
7. Sew shoulder seams, inserting the Front between the Back and the Facing, press towards the back and serge. Sew side seams, press seam allowances towards back, serge.
8. Sew sleeve seam, press seam allowances towards back, serge.
9. Sew sleeves into armholes matching notches, adjusting ease along upper side of sleeve cap. Serge and press. Sew shoulder pads.
10. Serge the lower edge of garment and lower edge of sleeve, press onto wrong side and finish with hidden stitches.

11. Make buttonhole on right front, on left front sew on button.

Congratulations, your jacket is ready! :)