

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2607 Dress with Decorative Seams

Recommendations on fabric: dress fabrics made from non-fraying materials made from natural or mixed fibers. (neoprene, capiton jersey, wool velor).

You will also need: fusible interfacing; dress zipper.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: Seam allowance for hem of garment – 1.5 cm. Seam allowance along upper edge of pocket – 2 cm. Other seams – 1 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Lower back – cut 2
4. Center front – cut 2
5. Side front – cut 2
6. Lower front – cut 2
7. Sleeve – cut 2

8. Cuff – cut 2
9. Collar – cut 1
10. Pocket – cut 2

Fusible interfacing:

1. Collar – cut 1
2. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing. Apply fusible interfacing to the upper edge of the pocket.
2. Fold the upper edge of the pocket to the wrong side and topstitch. Fold the side and lower seam allowances of the pocket to the wrong side and press. Pin the pocket to the front according to the markings and topstitch.
3. Sew the side back pieces to the center back. Sew the side front pieces to the center front, pinning the pieces wrong sides together. Trim the seam allowances to 0.2–0.3 cm.
4. Sew the lower front pieces to the upper front pieces and the lower back pieces to the upper back pieces, pinning the pieces wrong sides together. Trim the seam allowances to 0.2–0.3 cm.
5. Sew the center front seam, pinning the pieces wrong sides together. Trim the seam allowances to 0.2–0.3 cm.
6. Sew the side and shoulder seams. Press the seam allowances toward the back.
7. Sew the center back seam from the zipper marking to the hem and press the seam allowances open. Sew the outer collar to the neckline. Insert the zipper up to the middle of the collar. Fold the seam allowance of the inner collar to the wrong side and stitch in the ditch along the outer collar seam. Sew the center seam allowance of the collar to the zipper tape by hand.
8. Sew the sleeve seams and press the seam allowances. Sew each cuff into a ring and press the seam allowances open. Fold the cuff in half lengthwise, right side out, and press. Sew the outer cuff edge to the sleeve. Fold the seam allowance of the inner cuff to the inside and stitch in the ditch along the outer cuff seam.
9. Set the sleeves into the armholes and press the seam allowances.
10. Press the garment hem allowance to the wrong side and topstitch.

Congratulations – your dress are finished! :)