

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2620 A-Line Dress with Contrast Collar

Recommendations on fabric: natural/mixed knit fabric of small stretchiness in contrasting or similar color.

You will also need: knit fusible interfacing; dress zipper.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm; seam allowance for hem of garment – 2 cm.

Main fabric:

1. Upper center back – cut 2
2. Upper side back – cut 2
3. Lower back – cut 2
4. Upper center front – cut 1 on fold
5. Upper side front – cut 2
6. Lower front – cut 1 on fold
7. Sleeve – cut 2
8. Back neck facing – cut 1

9. Front neck facing – cut 1

Main fabric 1:

1. Collar – cut 2
2. Cuff – cut 2

Fusible interfacing:

1. Collar – cut 1
2. Cuff – cut 2
3. Back neck facing – cut 1
4. Front neck facing – cut 1

INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. Apply fusible interfacing.
2. Sew the princess seams on the upper back. Press the seam allowances toward the center and serge. Sew the upper back to the lower back. Press the seam allowances upward and serge.
3. Serge the center back edges separately. Sew the center back seam from the neckline to the first marking and from the second marking to the hem. Press the seam allowances open and insert the zipper.
4. Sew the princess seams on the upper front. Press the seam allowances toward the center and serge. Sew the upper front to the lower front. Press the seam allowances upward and serge.
5. Sew the side and shoulder seams. Press the seam allowances toward the back and serge.
6. Pin the collar pieces together, right sides facing, and sew the collar ends and collar fall. Clip into the curves, trim the corners, turn the collar right side out, and press. Sew the collar into the neckline.
7. Sew the shoulder seams of the neckline facings and press the seam allowances open. Serge the outer edge. Pin the facing to the garment, right sides together, placing the collar between the facing and the garment, and sew the neckline. Clip into the curves, turn the facing to the wrong side, and press. Slipstitch it to the shoulder seams.
8. Sew the sleeve seams. Press the seam allowances toward the back and serge. Set the sleeves into the armholes, serge the seam allowances, and press.
9. Sew each cuff into a ring and press the seam allowances open. Fold the cuff in half lengthwise, right side out. Sew the cuff to the lower edge of the sleeve. Press the

seam allowances toward the sleeve and serge.

10. Serge the lower edge of the dress, press it to the wrong side, and topstitch.

Congratulations – your dress are finished! :)