

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2624 Cold-Shoulder Blouse

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 10 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance along the lower edge of the garment – 2 cm.

Main fabric:

1. Back – cut 1
2. Front – cut 1
3. Right sleeve – cut 1
4. Collar – cut 2
5. Stand collar – cut 2
6. Cuff – cut 2

Fusible interfacing:

1. Stand collar – cut 1
2. Collar – cut 1
3. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing. Also apply fusible interfacing to the one-piece placket of the left sleeve.
2. Fold the one-piece placket of the left sleeve to the wrong side and press. Fold the seam allowance to the inside and topstitch 0.1 cm from the fold. Pin the front sleeve to the back sleeve, matching the buttonhole lines, and baste together along the lower edge.
3. Sew the right shoulder seam. Press the seam allowances toward the back and serge. Sew the sleeve to the garment. Press the seam allowances upward and serge.
4. Pin the collar pieces together, right sides facing, and sew the ends and outer edge of the collar. Trim the corners, turn the collar right side out, shape, and press. Pin the collar stand pieces together, right sides facing, inserting the finished collar between them, and sew, stitching the collar stand ends at the same time. Start and stop stitching exactly at the marked seam line between the collar stand and garment. Turn the collar stand right side out and press. Sew the outer collar stand to the neckline. Fold the open edge of the inner collar stand to the inside and stitch in the ditch.
5. Serge the side edges and sleeve edges separately on each piece. Sew the side seams, continuing along the sleeve seams, from the slit marking to the lower edge. Press the seam allowances open. Topstitch the slit 0.1 cm from the edge.
6. Fold each cuff in half lengthwise, right sides together, and sew the side seams. Turn the cuffs right side out and press. Sew the outer cuff edge to the sleeve. Fold the inner cuff edge to the inside and stitch in the ditch along the outer cuff seam.
7. Serge the lower edge of the garment, press it to the wrong side, and topstitch.
8. Make buttonholes and sew buttons on the plackets and collar stand. Make buttonholes and sew buttons on the cuffs.

Congratulations – your blouse are finished! :)