

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2642 Short Jacket with Two Buttons

Recommendations on fabric: thin natural/mixed suiting fabrics.

You will also need: lining; fusible interfacing; shoulder pads; 2 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm. Seam allowance along hem of jacket and hem of sleeve – 3 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Sleeve – cut 2
4. Collar – cut 1
5. Back neck facing – cut 1
6. Center front facing – cut 2

Lining:



1. Back – cut 1 on fold
2. Front – cut 2
3. Sleeve – cut 2

Fusible interfacing:

1. Center front facing – cut 2
2. Back neck facing – cut 1

Attention! Cut Back and Front from lining using the corresponding pieces for main fabric except for the width of back neckline facing and front neckline facing.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the darts on the back and front. Press the waist dart excess toward the center and the bust dart excess upward.
3. Sew the shoulder and side seams. Press the seam allowances open.
4. Fold the collar in half lengthwise, right sides together, and sew the short edges. Trim the corners, turn the collar right side out, shape, and press. Sew the collar into the neckline.
5. Sew the shoulder seams of the back neckline facing and center front facings. Press the seam allowances open. Pin the center front facings and back neckline facing to the garment, right sides together, and sew the center front edges, neckline, and lower center front corners. Trim the corners. Understitch the center front seam allowances to the facings 0.2 cm from the seam. Turn the facings to the wrong side, shape the seams, and press. Press the lower edge of the garment.
6. Sew the sleeve seams and press the seam allowances open. Set the sleeves into the armholes, matching the notches, and press the seams. Sew in the shoulder pads.
7. Assemble the lining in the same way as the main fabric, leaving an opening in the left sleeve seam. Sew the lining to the center front facings and back neckline facing. Press the seam allowances toward the facings. Sew the lining to the garment hem and sleeve hems. Turn the jacket right side out through the opening and sew the opening closed.
8. Make buttonholes on the right front and sew the buttons onto the left front.

Congratulations – your jacket are finished! :)