

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2660 Blouse with Batwing Sleeves and Shirt Collar

Recommendations on fabric: natural/mixed fabrics suitable for blouses in contrasting or similar color.

You will also need: fusible interfacing; 8 push buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance along the lower edge of the garment – 2 cm.

Main fabric:

1. Back – cut 2
2. Front – cut 2

Main fabric 1:

1. Back yoke – cut 1
2. Center front – cut 2
3. Collar – cut 2
4. Stand collar – cut 2
5. Cuff – cut 2

Fusible interfacing:

1. Stand collar – cut 1
2. Collar – cut 1
3. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing. Also apply fusible interfacing to the one-piece center front placket.
2. Sew the center back seam. Press the seam allowances toward the left and serge. Sew a gathering stitch along the upper edge of the back from the shoulder seam to the marking and gather the fullness. Sew the yoke to the back. Press the seam allowances toward the yoke and serge. Sew a decorative topstitch 0.1 cm from the seam.
3. Sew a gathering stitch along the princess seam edge of the front from the shoulder seam to the marking and gather the fullness. Sew the center front piece to the front. Press the seam allowances toward the center front piece and serge. Sew a decorative topstitch 0.1 cm from the seam.
4. Sew the shoulder seams and upper sleeve seams in one continuous seam. Press the seam allowances toward the back and serge.
5. Pin the collar pieces together, right sides facing, and sew the ends and outer edge of the collar. Trim the corners, turn the collar right side out, shape, and press. Pin the collar stand pieces together, right sides facing, inserting the finished collar between them, and sew, stitching the collar stand ends at the same time. Start and stop stitching exactly at the marked seam line between the collar stand and garment. Turn the finished collar stand right side out and press. Fold the one-piece placket to the wrong side and press. Sew the outer collar stand to the neckline. Fold the open edge of the inner collar stand to the inside and stitch in the ditch.
6. Serge the side and sleeve edges separately on each piece. Sew the side seams and sleeve seams in one continuous seam from the slit marking to the lower edge. Press the seam allowances open. Topstitch the slit 0.1 cm from the edge. Sew a gathering stitch along the lower edge of each sleeve and gather the fullness.
7. Fold each cuff in half lengthwise, right sides together, and sew the side edges. Turn the cuffs right side out and press. Sew the outer cuff edge to the sleeve. Fold the inner cuff edge to the inside and stitch in the ditch along the outer cuff seam.
8. Serge the lower edge of the garment, press it to the wrong side, and topstitch.
9. Sew the upper parts of the snap fasteners to the inner side of the right front and the lower parts to the left front. Sew the snap fasteners onto the cuffs.

Congratulations – your blouse are finished! :)