

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2665 Shirt Jacket

Recommendations on fabric: natural/mixed soft suiting fabrics and corduroy in two matching colors.

You will also need: fusible interfacing; 9 buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: Seam allowance for hem of garment – 2 cm, seam allowance along upper edge of pocket – 2 cm, other seams – 1 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front right – cut 1
3. Front yoke – cut 2
4. Sleeve – cut 2
5. Collar – cut 2
6. Cuff – cut 2
7. Center front facing – cut 2
8. Back neck facing – cut 1

9. Pocket – cut 2

10. Flap – cut 4

Main fabric 1:

1. Front left – cut 1

2. Back yoke – cut 1

Fusible interfacing:

1. Center front facing – cut 2

2. Collar – cut 1

3. Cuff – cut 2

4. Back neck facing – cut 1

5. Flap – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the back yoke to the back. Serge the seam allowances and press them upward.
3. Pin the pocket flap pieces together in pairs, right sides facing, and sew the side and lower edges. Trim the seam allowances, turn the flaps right side out, and press.
4. Serge the upper edge of each pocket. Fold the seam allowance to the wrong side and topstitch. Fold the side and lower edges of the pockets to the wrong side and press. Pin the pockets to the front pieces according to the markings and topstitch.
5. Sew the front yokes to the front pieces, inserting the pocket flaps. Serge the seam allowances and press them upward.
6. Sew the side and shoulder seams. Press the seam allowances toward the back and serge.
7. Pin the upper collar to the lower collar, right sides together. Sew the collar ends and outer edge. Trim the seam allowances, turn the collar right side out, shape, and press.
8. Sew the shoulder seams of the back neckline facing and center front facings. Press the seam allowances open and serge the outer edges.
9. Pin the center front facings and back neckline facing to the garment, right sides together, and baste along the seams. Sew the center front edges and neckline, inserting the collar. Turn the facings to the wrong side and press the center front edges. Baste the shoulder edges of the facings to the garment.
10. Cut the sleeve slit along the marked line. Cut bias tape from the main fabric or use ready-made bias tape 4 cm wide and long enough to equal twice the slit length plus 4 cm. Fold the bias tape in half lengthwise and press. Press the long edges toward the center. Pin the bias tape to the sleeve slit from the right side and sew. Fold the bias tape to the wrong side and topstitch along the fold line.

11. Sew the sleeve seams. Press the seam allowances toward the back and serge.
12. Fold the cuffs in half lengthwise, right sides together, and sew the side edges and corners. Start and stop stitching exactly at the marked cuff seam lines. Turn the cuffs right side out and press. Sew the outer cuff edge to the sleeve. Fold the inner cuff edge to the inside and stitch in the ditch along the outer cuff seam. Sew the sleeves into the armholes, serge the seam allowances, and press. Sew a gathering stitch along the lower edge of each sleeve and gather the fullness.
13. Serge the lower edge of the garment, turn it to the wrong side, and topstitch.
14. Make buttonholes on the right front, cuffs, and pocket flaps. Sew the buttons onto the left front, pockets, and cuffs.

Congratulations – your jacket are finished! :)