

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.


Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2670 Jersey Dress with Draping

Recommendations on fabric: natural/mixed well draping knit fabric of medium or high stretchiness.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm; seam allowance for hem of garment – 1.5 cm.

Main fabric:

1. Back – cut 1
2. Side back – cut 1
3. Front – cut 1
4. Side front – cut 1

INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. On the front piece, sew gathering stitches between the first and second markings

and between the third and fourth markings, then gather the fullness. On the side front piece, sew a gathering stitch between the markings and gather the fullness. Use the side front control pattern piece to check the correct gathered length.

2. Sew the left shoulder seam. Press the seam allowances toward the back and serge.
3. Serge the outer edge of the one-piece neckline facing. Turn the facing to the wrong side and press. Secure it by hand along the seams.
4. Sew the right shoulder seam of the side pieces. Press the seam allowances toward the back and serge.
5. Sew the side back pieces to the back and the side front pieces to the front. Press the seam allowances away from the center and serge. Topstitch non-elastic tape to the seam allowances to prevent stretching. Sew a topstitch 0.1 cm from the seam.
6. Cut or use ready-made bias tape 4 cm wide and long enough to match the armhole length plus 4 cm. Fold the bias tape in half lengthwise, right side out, and press. Pin the bias tape to the armhole edge from the right side and sew. Fold the bias tape to the wrong side and topstitch along the seam from the right side.
7. Sew the side seams. Press the seam allowances toward the back and serge.
8. Serge the lower edge of the garment, press it to the wrong side, and topstitch.

Congratulations – your dress are finished! :)