

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2673 Jacket with Asymmetrical Zip Closure

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; 1 separating zipper; lining.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm. Seam allowance for hem of sleeve – 2 cm.

Main fabric:

1. Center back – cut 1 on fold
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Sleeve – cut 2
6. Right placket – cut 1
7. Left placket – cut 1
8. Center front facing – cut 2



9. Back neck facing – cut 1
10. Collar – cut 2

Fusible interfacing:

1. Center front – cut 2
2. Collar – cut 1
3. Center front facing – cut 2
4. Back neck facing – cut 1

Lining:

1. Center back – cut 1 on fold
2. Side back – cut 2
3. Front lining – cut 2
4. Sleeve – cut 2

Attention: Back lining is cut using the pattern pieces for the main fabric, except for the width of back neckline facing.

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the side back pieces to the center back. Press the seam allowances away from the center. Sew a decorative topstitch 0.5 cm from the seam.
3. Sew the right side front to the center front. Press the seam allowances away from the center. Sew a decorative topstitch 0.5 cm from the seam.
4. Sew the side seams.
5. Sew the upper edge of the right placket to the lower edge of the jacket. Sew the upper edge of the left placket to the left front.
6. Sew the left side front to the center front, inserting the zipper. Position the lower end of the zipper in the center of the placket width. Press the seam allowances away from the center. Sew a decorative topstitch 0.5 cm from the seam. Sew the right zipper tape to the edge of the right front, with the teeth facing away from the edge. Position the lower end of the zipper in the center of the placket width.
7. Sew the shoulder seams and press the seam allowances open. Sew the upper collar into the neckline, starting and stopping exactly at the marked seam lines. Press the seam allowances open.
8. Sew the darts on the sleeves. Trim the dart excess and press the seam allowances open. Set the sleeves into the armholes and press the seam allowances toward the garment. Sew a decorative topstitch 0.5 cm from the seam.
9. Sew the shoulder seams of the center front facings and back neckline facing. Press the seam allowances open. Sew the lower collar into the neckline of the center front

facings and back neckline facing, starting and stopping exactly at the marked seam lines. Press the seam allowances open.

10. Assemble the lining and set in the sleeves, leaving an opening in the right side seam. Press the lining seam allowances. Sew the lining to the center front facings and back neckline facing, then press the seam allowances.

Pin the lining to the garment, right sides together, and sew the lower edge of the placket. Fold the placket upward, enclosing the zipper. Sew the center front facings, lapels, collar, and sleeve hems. Clip into the curves, trim the corners, and turn the garment right side out. Sew the placket seam allowances together by hand. Sew a decorative topstitch 0.5–0.7 cm from the center front edge.

11. Sew the opening in the side seam closed.

Congratulations – your jacket are finished! :)