

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2675 Long Vest with Lapels

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; lining; two buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance for hem of garment – 2.5 cm.

Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2
5. Lower collar - cut 1
6. Upper collar – cut 1
7. Center front facing – cut 2
8. Back neck facing – cut 1

Attention: lining for front and back is cut using the pattern blocks for main fabric except

for the width of the center front facing and back neckline facing.

Lining:

1. Center back – cut 2
2. Side back – cut 2
3. Center front – cut 2
4. Side front – cut 2

Fusible interfacing:

1. Center front – cut 2
2. Center front facing – cut 2
3. Back neck facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing. Apply a 1 cm wide strip of fusible interfacing along the lapel fold lines on the front pieces.
 2. Sew the center back seam and press the seam allowances open. Sew the side back pieces to the center back. Press the seam allowances toward the center.
 3. Sew the side front pieces to the center front. Press the seam allowances toward the center.
 4. Sew the shoulder and side seams. Press the seam allowances open.
 5. Pin the upper collar to the lower collar and sew the corners and outer edge. Start and stop stitching exactly at the marked seam lines between the collar and the garment. Trim the corners and clip into the seam allowances near the markings. Turn the collar right side out, shape, and press.
 6. Sew the shoulder seams of the back neckline facing and center front facings. Press the seam allowances open.
 7. Place the center front facings onto the front pieces, right sides together, and sew along the center front edges up to the notches marking the ends of the collar seam.
 8. Sew the lower collar into the vest neckline. Sew the upper collar into the neckline of the back facing and center front facings. Press the collar seam allowances open and slipstitch them together close to the seam.
 9. Fold the lower edge of the vest to the wrong side and press.
 10. Assemble the lining, leaving an opening in the left side seam. Sew the lining to the center front facings and back neckline facing. Sew the armholes in two steps: first sew the front armholes, then the back armholes. Clip the seam allowances and press. Sew the lining to the lower edge of the vest.
 11. Turn the vest right side out through the opening. Sew the opening closed.
 12. Make buttonholes on the right front and sew the buttons onto the left front.
- Congratulations – your vest are finished! :)