

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2678 Cropped Wrap Blouse

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 1 button.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance for hem of garment and hem of sleeve – 3 cm.

Main fabric:

1. Back – cut 2
2. Front – cut 2
3. Sleeve – cut 2
4. Back neck facing – cut 1
5. Center front facing – cut 2
6. Belt – cut 2

Fusible interfacing:

1. Back neck facing – cut 1
2. Center front facing – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the darts on the back and press the dart excess toward the center. Sew the center back seam, press the seam allowances toward the left, and serge.
3. Sew the darts on the front. Trim the dart excess, press it toward the center, and serge.
4. Fold the belts in half lengthwise, right sides together, and sew along one short edge and the long edge.
5. Sew the shoulder and side seams, inserting one belt into the left side seam. Press the seam allowances toward the back and serge.
6. Sew the shoulder seams of the back neckline facing and center front facings. Press the seam allowances open and serge the outer edge. Pin the center front facings and back neckline facing to the garment, right sides together, inserting the right belt, and sew the center front edges and neckline. Clip into the curves, turn the facings to the wrong side, shape, and press. Topstitch the center front facings and back neckline facing to the garment.
7. Sew the sleeve seams. Press the seam allowances toward the back and serge. Set the sleeves into the armholes, matching the notches. Serge the seam allowances and press.
8. Press the garment hem and sleeve hems to the wrong side by 1 cm, then by another 2 cm, and topstitch.
9. Make a buttonhole on the left front. Sew a concealed button to the wrong side of the right front.

Congratulations – your blouse are finished! :)