

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.


Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2681 Jacket with Cape Sleeves and Asymmetrical Lapels

Recommendations on fabric: natural/mixed stable fabrics.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance along hem and along center front edge – 0 cm. Seam allowance along the lower edge of the armhole, seam allowances of the sleeve EXCEPT for the upper part of the sleeve cap – 0 cm. Outer seam allowances of collar – 0 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Sleeve – cut 2
4. Collar – cut 1

INSTRUCTIONS:

1. Trim away the neckline and lapel seam allowances on the right front.
2. Sew the side and shoulder seams. Trim the seam allowances to 0.5 cm and press them open.
3. Pin the right front to the right collar piece and topstitch along the marked line. Clip into the seam allowance at the corner.
4. Clip into the collar seam allowances according to the markings. Sew the collar into the back neckline. Trim the seam allowances to 0.5 cm and press them open. Sew the collar to the neckline of the left front, pinning the pieces wrong sides together so that the seam allowances remain on the right side of the garment. Trim the seam allowances to 0.5 cm and press them open.
5. Sew the sleeve into the upper section of the armhole. Press the seam allowances.

Congratulations – your jacket are finished! :)