

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 2682 Jacket with Peplum and Asymmetrical Button Closure

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; lining; shoulder pads; 6 buttons.

### CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance for hem of garment and hem of sleeve – 3 cm.

### Main fabric:

1. Center back – cut 2
2. Side back – cut 2
3. Lower back – cut 1
4. Front – cut 2
5. Lower front – cut 2
6. Collar – cut 2
7. Center front facing – cut 2

8. Back neck facing – cut 1
9. Upper sleeve – cut 2
10. Lower sleeve – cut 2

Lining:

1. Center back – cut 2
2. Side back – cut 2
3. Lower back – cut 1
4. Front – cut 2
5. Lower front – cut 2
6. Upper sleeve – cut 2
7. Lower sleeve – cut 2

Lining is cut using pattern blocks for main fabric, except for the width of back neckline facing and central front facings.

Fusible interfacing:

1. Front – cut 2
2. Lower front – cut 2
3. Collar – cut 1
4. Center front facing – cut 2
5. Back neck facing – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the side back pieces to the center back and press the seam allowances toward the center. Sew the center back seam and press the seam allowances open. Sew the upper back to the lower back and press the seam allowances downward.
3. Sew the darts on the front. Trim the dart excess to 1 cm and press it toward the center. Sew the upper front to the lower front and press the seam allowances downward.
4. Sew the shoulder and side seams. Press the seam allowances open.
5. Pin the collar pieces together, right sides facing, and sew the collar ends and outer edge. Clip into the curves and trim the corners. Turn the collar right side out, shape, and press. Sew the collar into the neckline.
6. Sew the shoulder seams of the center front facings and back neckline facing. Press the seam allowances open. Pin the center front facings and back neckline facing to the garment, right sides together, and sew the center front edges, neckline, and lower front corners, placing the collar between the facing and the garment. Clip into the curves, trim the corners, turn the facings to the wrong side, and press.

7. Sew the elbow seams of the sleeves and press the seam allowances open. Press the sleeve hem allowances. Sew the front sleeve seams and press the seam allowances open. Set the sleeves into the armholes, matching the notches and easing the fullness along the upper sleeve cap. Sew in the shoulder pads.
8. Assemble the lining in the same way as the main fabric, leaving an opening in the left sleeve elbow seam. Sew the lining to the back neckline facing and center front facings. Turn the garment right side out and shape the seams.
9. Mark the hem, turn it to the wrong side, and press. Sew the lining to the garment hem and sleeve hems. Sew the opening closed.
10. Sew decorative topstitching along the upper section of the center front edge according to the markings. Make buttonholes on the right front and sew the buttons onto the left front. Make the upper and lower inner buttonholes on the left front and sew the corresponding inner buttons onto the right front.

Congratulations – your jacket are finished! :)