

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.


2683 Blouse with Voluminous Sleeves and Tie Collar

Recommendations on fabric: Thick natural/mixed fabrics suitable for blouses. Thin denim fabrics.

You will also need: fusible interfacing; 11 push buttons.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams – 1 cm. Seam allowance along the lower edge of the garment – 2 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Back yoke – cut 1 on fold
4. Upper sleeve – cut 2
5. Lower sleeve – cut 2
6. Stand collar – cut 2
7. Cuff – cut 2
8. Tie – cut 2
9. Placket – cut 2

Fusible interfacing:

1. Stand collar – cut 1
2. Cuff – cut 2
3. Placket – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the yoke to the back. Press the seam allowances toward the yoke and serge. Sew a decorative topstitch 0.5 cm from the seam.
3. Sew the dart on the front and press the dart excess upward.
4. Sew the outer edge of the placket to the front and press the seam allowance toward the placket. Fold under the seam allowance of the inner placket and stitch in the ditch. Sew decorative topstitching along the placket 0.5 cm from the edge and 0.5 cm from the seam.
5. Sew the shoulder and side seams. Press the seam allowances toward the back and serge.
6. Pin the collar stand pieces together, right sides facing, and sew the ends and outer edge. Trim the corners, turn the collar stand right side out, shape, and press. Sew the outer collar stand to the neckline. Fold the open edge of the inner collar stand to the inside and stitch in the ditch. Sew decorative topstitching around all edges of the collar stand 0.5 cm from the edge.
7. Sew gathering stitches along the upper and lower edges of the lower sleeves and gather the fullness. Sew the upper sleeves to the lower sleeves. Serge the seam allowances and press them upward. Sew a decorative topstitch 0.5 cm from the seam. Serge the sleeve edges separately. Sew the sleeve seams from the upper edge to the slit marking. Press the seam allowances open. Topstitch the slit 0.1 cm from the edge.
8. Fold the cuffs in half lengthwise, right sides together, and sew the side edges. Turn the cuffs right side out and press. Sew the outer cuff edge to the sleeve. Fold the inner cuff edge to the inside and stitch in the ditch along the outer cuff seam. Sew decorative topstitching around all cuff edges 0.5 cm from the edge.
9. Fold the tie in half lengthwise, right sides together, and sew along the long edge and shaped end. Turn the tie right side out and press. Sew decorative topstitching around all edges 0.5 cm from the edge. Serge the short edge. Fold the serged edge to the wrong side and topstitch the tie to the collar stand with two parallel stitch lines near the shoulder seam.
10. Serge the lower edge of the garment, press it to the wrong side, and topstitch.
11. Install snap fasteners on the front pieces, collar stand, and cuffs.

Congratulations – your blouse are finished! :)