

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2772 Dress with Stand Collar and Cuffs

Recommendations on fabric: natural/mixed fabric suitable for dresses.

You will also need: fusible interfacing; 11 buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seam allowances – 1 cm, seam allowance along hem of garment – 3 cm.

Main fabric:

1. Upper back – cut 1 on fold
2. Lower back – cut 1 on fold
3. Upper front – cut 2
4. Lower front – cut 2
5. Sleeve – cut 2
6. Placket – cut 2
7. Stand collar – cut 2
8. Cuff – cut 2

Fusible interfacing:

1. Placket – cut 2



2. Stand collar – cut 1
3. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew darts on upper fronts, press bulk towards top.
3. Sew the side seams of the upper parts of the dress, press seams apart, serge. Sew the side seams of the lower parts of the dress, press seams apart, serge.
4. Sew a gathering stitch along the upper edge of the lower front and gather fullness. Sew a gathering stitch along the upper edge of the lower back and gather fullness. Sew lower part to upper part, press seam, serge. Make a pleat on the upper part of the dress and topstitch it into the seam between the lower and upper parts from the right side.
5. Sew shoulder seams, press seam allowances towards back and serge.
6. Fold placket in half lengthwise wrong sides together and press. Sew outer edge of placket to front, press seam allowances at placket. Turn seam allowance of inner side of placket under and topstitch into seam.
7. Pin stand collars together right sides together and sew upper and side edges. Start and stop stitching exactly at the marked line of the seam between stand collar and garment. Turn the piece right side out, straighten and press. Sew outer stand collar into neckline, fold inside open edge of inner stand collar and stitch in the ditch.
8. Sew sleeve seam, press towards back and serge. Sew sleeves into armholes matching notches, serge and press.
9. Sew cuff into a ring, press seam apart. Fold cuff in half lengthwise wrong sides together and press. Sew outer part of cuff to sleeve, fold inside the inner side of cuff, and topstitch into the seam of the outer cuff.
10. Serge seam allowance for hem, press onto wrong side and topstitch.
11. Make buttonholes on the right placket and the right stand collar. Sew on buttons according to buttonholes.
Congratulations – your dress are finished! :)