

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2801 Short coat with stand-up collar and pockets

Recommendations on fabric: thin coat or natural/mixed suiting fabrics.

You will also need: fusible interfacing; decorative closure with a buckle, button.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance for hem of garment and hem of sleeve – 3 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Sleeve – cut 2
4. Center front facing – cut 2
5. Back neck facing – cut 1
6. Stand collar – cut 2
7. Pocket welt – cut 2

Lining:

1. Front lining – cut 2
2. Back lining – cut 1 on fold
3. Sleeve – cut 2
4. Large pocket bag – cut 2
5. Small pocket bag – cut 2

INSTRUCTIONS:

1. Fold the off-set welt in half lengthwise, right sides together, and sew along the shorter edges. Clip into the seam allowances at the corners, turn the off-set welt right side out, and press. Topstitch along the shorter sides and one longer side.
2. Apply fusible interfacing to the pocket opening area. Topstitch the small pocket bag onto the inner side of the welt. Pin the pocket welt to the right side of the front along the marked line, positioning the welt closer to the center front. Sew the off-set welt. Sew the larger pocket bag to the other marked line of the pocket. Slash the pocket opening between the stitching lines, cutting diagonally into the corners. Turn the pocket bags to the inside. Straighten the seam allowances and press. Sew the edges of the pocket bags together, securing the corners. Topstitch the pocket welt along the side edges from the right side of the garment.
3. Sew the shoulder seams and press them open.
4. Sew the side seams from the armhole down to the notch for the slit. Serge and press the seams open. Sew a reinforcing stitch along the slit, 0.5 cm from the edge.
5. Make a buttonhole on the right center front facing. Sew the side seams of the center front facings and back neckline facings. Press the seams open. Pin the center front facing to the front, right sides together, and sew along the front edge and neckline up to the center front line. Clip into the seam allowance near the notch, trim the corners, turn the facings to the inside, and press.
6. Pin the two pieces of the stand collar together, right sides facing, and sew along the ends and outer edge. Start and stop stitching exactly at the marked seam line. Clip into the seam allowances, trim the corners, turn the collar right side out, straighten, and press. Sew the outer stand collar to the neckline of the garment. Sew the inner stand collar to the neckline of the facings. Press the collar seam allowances apart and baste close to the seam.
7. Sew the sleeve seams and press them open. Insert the sleeves into the armholes,

matching notches.

8. Sew the lining pieces together and insert the sleeves. Fold the hem seam allowance of the lining twice by 1 cm, press, and topstitch.
9. Sew the lining to the center front facings and back neckline facing. Press the seam. Serge the seam from the armhole level down to the hem. Sew the sleeve lining to the sleeve hem. Turn the garment right side out and straighten the seams.
10. Serge and press the lower edge of the coat. Sew the center front facing to the front hem corner. Topstitch the lower edge.
11. Topstitch the decorative closure. Sew the inner button onto the left front to match the buttonhole.

Congratulations, your coat is ready! :)