

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2811 Blouse with Batwing Sleeves and Yoke

Recommendations on fabric: natural/mixed fabrics suitable for blouses. Chiffon, silk.

You will also need: fusible interfacing, 7 buttons.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance along the lower edge of the garment – 2 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Yoke – cut 2
4. Placket – cut 2
5. Collar – cut 2
6. Stand collar – cut 2
7. Cuff – cut 2

Fusible interfacing:

1. Placket – cut 2
2. Collar – cut 1
3. Stand collar – cut 1
4. Cuff – cut 2

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew a gathering stitch along the upper edge of the front between the markings and gather fullness. Sew the front yoke to the front. Serge and press onto the yoke.
3. Sew the outer edge of the placket to the front, press the seam allowance toward the placket. Fold under the seam allowance of the inner side and topstitch into the seam.
4. Sew side and shoulder seams, stitching the sleeve edges at the same time. Press seams toward the back and serge.
5. Pin collars together, right sides together, and sew the ends and the outer edge of the collar. Trim away corners. Turn the collar right side out, straighten and press. Sew a decorative stitch at 0.1 cm from the edge. Pin stand collars together, right sides together, insert the finished collar between them and sew, stitching the ends of the stand collar at the same time. Start and stop sewing exactly at the marked seam line between the stand collar and the garment. Turn the finished collar right side out and press. Sew the outer stand collar into the neckline, fold the open edge of the inner stand collar inside and stitch in the ditch.
6. Fold the cuff in half lengthwise, right sides together, and sew the short sides. Trim seam allowances in corners, turn right side out and press. Sew the cuff to the sleeve. Serge the seam allowances and press toward the sleeve.
7. Serge the lower edge of the garment. Press the seam allowance to the wrong side and topstitch.
8. Make buttonholes and sew on buttons on the placket and on the stand collar.

Congratulations, your blouse is ready! :)