

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2815 Blouse with Decorative Front Detail

Recommendations on fabric: natural/mixed fabrics suitable for blouses.

You will also need: fusible interfacing; 1 button.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: seam allowance for hem of garment – 2 cm; other seams – 1 cm.

Main fabric:

1. Back – cut 2
2. Front – cut 1
3. Placket – cut 1
4. Flounce – cut 2
5. Back neck facing – cut 2
6. Front neck facing – cut 1

Fusible interfacing:

1. Back neck facing – cut 2
2. Front neck facing – cut 1
3. Placket – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.

2. Sew front darts, pressing bulk towards the top.
3. Serge the center back edges separately. Sew the center back seam from the slit marking down to the hem, and press the seam open.
4. Pin the flounces right sides together and sew along the two long straight sides. Turn the flounce right side out and press. Pin the flounce to the front and topstitch the short section between the marks. Press the seam allowance of this section towards the center.
5. Fold the seam allowances along the long side of the placket to the wrong side and press. Pin the placket onto the front and topstitch along the long edges, covering the flounce seam allowance. Baste the seam allowances of the flounces and the front together along the shoulder edges, armholes, and neckline. Press the flounce folds.
6. Sew shoulder seams, press towards the back, and serge.
7. Sew the shoulder seams of the neckline facings, press the seams open, and serge the outer edge. Pin the facing to the right side of the garment and sew the neckline. Clip seam allowances, trim corners, turn the facing to the wrong side, straighten, and press. Hand-stitch the facing to the shoulder seams.
8. Cut (or use ready-made) bias tape, 2.5 cm wide and 10 cm long, for the loop buttonhole. Fold the tape in half lengthwise, right sides together, and stitch 0.3 cm from the fold. Trim seam allowances close to the seam, turn the tape right side out, and straighten. Adjust the loop length. Insert the button loop between the back and the facing and secure by hand.
9. Cut (or use ready-made) bias tape, 4 cm wide and equal in length to the armhole + 4 cm. Fold the tape in half lengthwise, right side out, and press. Pin the tape to the armhole edge from the right side and sew. Clip seam allowances, fold the tape to the wrong side, and topstitch onto the garment along the seam. Press.
10. Sew side seams, press towards the back, and serge.
11. Turn the hem to the inside twice, 1 cm each time, and topstitch.
12. Sew a button onto the right back.

Congratulations, your blouse is ready! :)