

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2850 Feminine Jacket with Gathered Peplum

Recommendations on fabric: natural/mixed suiting fabrics.

You will also need: fusible interfacing; shoulder pads; 4 hooks and eyes.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm. Seam allowance along the hem of the jacket – 2 cm. Seam allowance on lower edge of sleeve – 3 cm.

Main fabric:

1. Upper back – cut 2
2. Lower back – cut 1 on fold
3. Front – cut 2
4. Placket – cut 1
5. Upper sleeve – cut 2
6. Lower sleeve – cut 2
7. Stand collar – cut 2



8. Back neck facing – cut 1
9. Center front facing – cut 2

Fusible interfacing:

1. Placket – cut 1
2. Center front facing – cut 2
3. Back neck facing – cut 1
4. Stand collar – cut 1

INSTRUCTIONS:

1. Apply fusible interfacing.
2. Sew the back darts, trim the dart excess to 1 cm, press toward the center, and serge. Sew the center back seam, press toward the left, and serge.
3. Sew a gathering stitch along the upper edge of the lower back and gather the fullness. Sew the upper back to the lower back, press upward, and serge.
4. Trim the dart excess on the front pieces to 1 cm. Sew the darts, press the excess toward the center, and serge.
5. Sew a gathering stitch along the upper edge of the one-piece front peplum and gather the fullness. Sew the upper front to the lower front, press upward, and serge.
6. Sew the shoulder and side seams, press toward the back, and serge.
7. Pin the stand collar pieces right sides together and sew the ends and upper edge. Trim the corners, clip the curves, turn the stand collar right side out, shape, and press. Sew the stand collar into the neckline.
8. Fold the placket in half lengthwise, right sides together, and sew the short ends. Turn the placket right side out, shape, and press.
9. Sew the side seams of the back neckline facing and the center front facings, press the seams open, and serge the outer edge. Pin the center front facings to the garment, right sides together, and sew the center front edge, neckline, and lower edge, inserting the placket and loops between the left center front facing and the front. Trim the corners, clip the curves, turn the center front and neckline facings to the wrong side, shape, and press. Hand-stitch the facings to the shoulder seams and the center back seam.
10. Sew the elbow seam and the front seam of the sleeves. Press the seam allowances upward and serge. Sew the sleeves into the armholes, matching the notches and easing the sleeve caps. Serge and press. Sew in the shoulder pads.
11. Serge the hem allowances of the garment and sleeves, turn them to the wrong side, and topstitch.
12. Sew the hooks to the right front, aligning them with the eyes.

Congratulations – your jacket are finished! :)



Model 2850

pattern from pppp.dk