

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 4124 Long robe

Recommendations on fabric: natural/mixed terry fabric.

You will also need: .

### CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm. Seam allowance of upper edge of pocket – 4 cm. Seam allowance along center front, hem of garment and hem of sleeve – 3 cm.

### Main fabric:

1. Back – cut 1 on fold
2. Front – cut 2
3. Buttonstand – cut 2
4. Collar – cut 1
5. Sleeve – cut 2
6. Belt – cut 1

## INSTRUCTIONS:

1. Sew the darts on the front. Trim the dart excess to 0.7 cm with a serger.
2. Serge the seam allowance along the upper edge of the pocket, press it to the wrong side, and topstitch. Serge the side and lower edges of the pocket and press them to the wrong side. Pin the pocket to the front and topstitch.
3. Sew the collar to the front pieces and press the seam allowances open.
4. Sew the shoulder seams of the front and back, clipping into the seam allowances near the corners. Press the seam allowances toward the back and serge. Sew the collar to the neckline and press the seam allowances toward the collar.
5. Sew the button stands (center front facings) together and press the seam allowances open. Serge the outer edge. Serge the center front edge, press it to the wrong side, and topstitch. Pin the button stand to the garment, right sides together, and sew along the collar edge. Clip the curves, turn the button stand to the wrong side, and press. Topstitch the button stand onto the front along the marked line and into the seam of the lower collar.
6. Set the sleeves into the armholes, matching notches. Serge and press the seam allowances. Sew the side seams, sewing the sleeve seams at the same time. Press the seam allowances toward the back and serge.
7. Serge the bottom edge of the garment and the sleeve hems. Press them to the wrong side and topstitch.
8. Fold the belt in half lengthwise, right sides together, and stitch along the long edge and one short edge. Turn the belt right side out, fold the seam allowance of the open edge under, and topstitch around the belt 0.7 cm from the edge.

Congratulations – your robe are finished! :)