

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

4346 Jersey dress with batwing sleeves

Recommendations on fabric: natural or mixed medium weight, medium to high stretch knit fabric.

You will also need: elastic thread.


CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: on hem and lower edge of sleeve – 2 cm, along back and front neckline – 1.5 cm, all other seams – 0.7 cm.

Main fabric:

1. Lower back – cut 2
2. Upper back – cut 2
3. Upper front – cut 1
4. Lower front – cut 1



INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. Sew the center back seam of the upper and lower back pieces and serge. Sew the upper and lower back pieces together and serge.
2. On the upper front, clip the seam allowance near the T-mark and the section between the T-marks. Form a pleat (with the depth directed upward) and stitch from the shoulder seam to the end of the pleat. Place the left front piece right side up along the marked long line, place it over the right front piece, matching the neckline and shoulder edges, and baste together. Sew the upper and lower front pieces together and serge.
3. Sew the upper sleeve seam and serge. Sew the lower sleeve seam together with the side seams and serge.
4. Serge the neckline seam allowance, turn it to the wrong side, and topstitch. Serge the dress hem and sleeve hems, turn to the wrong side, and topstitch.
5. Stitch with elastic thread along the sleeve seams from the hem up to the marked line.

ATTENTION! For some sizes, the upper front may not fit on the fabric. In this case, you will need to cut along the line on the sleeve and cut the upper front in two pieces. Do not forget to add seam allowances!

Congratulations – your dress are finished! :)