If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

4479 Dress with Lace Yoke



Recommendations on fabric: natural/mixed fabric suitable for dresses; lace fabric.

You will also need: dress zipper.

CUTTING:

The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm. Seam allowance for hem of dress – 2 cm, seam allowance for hem of sleeve – 1.2 cm.

Main fabric:
1. Center back – cut 2
2. Side back – cut 2
3. Side front – cut 2
4. Center front – cut 1

Lace fabric:
1. Back yoke – cut 4
2. Front yoke – cut 2

3. Sleeve – cut 2
4. Lower gore – cut 2

INSTRUCTIONS:

1. Sew the side back pieces to the center back pieces. Press the seam allowances toward the center and serge. Sew the back yoke pieces to the back, press the seam allowances toward the yoke, and serge. Serge the center back edges separately. Sew the center back seam from the zipper marking to the hem, leaving the zipper opening unstitched. Press the seam allowances open, including those along the zipper opening. Insert the zipper.

2. Sew the lower gores to the center front piece. Press the seam allowances and serge. Sew the side front pieces to the center front. Press the seam allowances toward the center and serge. Sew the front yoke to the front, press the seam allowances toward the yoke, and serge.

3. Sew the shoulder and side seams. Press the seam allowances toward the back and serge.

4. Sew the shoulder seams of the inner yoke pieces. Press the seam allowances toward the back and serge. Serge the lower edge of the inner yoke.

5. Pin the inner yoke to the outer yoke, right sides together, and sew along the neckline. Clip the seam allowances along the curves. Turn the inner yoke to the wrong side, shape the neckline edge, and press. Secure the center back edges of the inner yoke to the zipper tape with slip stitches. Secure the inner yoke by stitching in the ditch along the outer yoke attachment seam. Treat the inner and outer yokes as a single layer during the remaining construction.

6. Serge the lower edges of the sleeves. Press the hem allowances to the wrong side and topstitch. Set the sleeves into the armholes and serge the seam allowances. Cut or use ready-made bias tape measuring 4 cm wide and equal in length to the lower armhole edge plus 6 cm. Fold the tape in half lengthwise, wrong sides together, and press. Pin the folded tape to the lower armhole edge on the right side of the dress and stitch in place. Turn the tape to the wrong side, clip the seam allowances where necessary, and secure it by topstitching along the attachment seam. Press.

7. Serge the lower edge of the dress. Press the hem allowance to the wrong side and topstitch.

Congratulations – your dress are finished! :)