

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5013 Classic women's jacket with pockets

Recommendations on fabric: costume fabric.

You will also need: fusing; 5-6 buttons; lining.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: all seams 1 cm.

Main fabric:

1. Flap – 4 pieces
2. Pocket valance – 2 pieces
3. Pocket facing – 4 pieces
4. Inner collar – 2 pieces
5. Outer collar – 1 folded piece
6. Center back part – 2 pieces
7. Side back part – 2 pieces
8. Back neckline facing – 1 folded piece
9. Side front part – 2 pieces
10. Front part – 2 pieces

11. Front band – 2 pieces
12. Upper sleeve – 2 pieces
13. Lower sleeve – 2 pieces

Lining:

1. Sacking – 4 pieces
2. Back part – 1 folded piece
3. Front part – 2 pieces
4. Upper sleeve – 2 pieces
5. Lower sleeve – 2 pieces

Fusing:

1. Flap – 2 pieces
2. Pocket valance – 2 pieces
3. Pocket facing – 4 pieces
4. Inner collar – 2 pieces
5. Outer collar – 1 folded piece
6. Back shoulder segment – 2 pieces
7. Side back part reinforcement – 2 pieces
8. Back neckline facing – 1 folded piece
9. Back hem allowance – 2 pieces
10. Side back part's hem allowance – 2 pieces
11. Side front part – 2 pieces
12. Front band – 2 pieces
13. Upper sleeve allowance – 2 pieces
14. Lower sleeve allowance – 2 pieces
15. Sleeve cap's reinforcement – 2 pieces

INSTRUCTIONS:

1. Front pieces: stitch the front princess seams down to the corners of the pocket openings. Cut the seam allowances on the center and side front pieces along the perpendicular edges at the pocket openings. Clip the seam allowance on the center front piece exactly up to the stitch line. Press the seam allowances open. Tack the pocket openings with cross stitches, matching the opening edges precisely.
2. Make the front welt pockets with flaps: stitch one reinforced flap piece and one unreinforced flap piece together along the side and lower edges. Turn right side out and topstitch along the edges. Apply a 4 cm wide strip of fusible interfacing to the wrong side of the pocket marking area. Place the two pocket facings on the front piece, right sides together, align them along the pocket marking, and stitch. The lengthwise edges of the facings must align with the center line of the pocket

marking. Cut the front piece between the stitching lines and clip diagonally to the ends of the stitching. Do not cut the facings. Press the slit seam allowances away from the pocket opening. Turn the facings to the wrong side through the slit to form a neat frame, aligning the folded edges of the facings with the center line of the pocket opening. Stitch along the joining seam. Turn the small triangles at the ends of the slit to the wrong side and stitch them neatly between the upper and lower stitching lines. Insert the raw edge of the flap between the facings and stitch it into the seam joining the upper facing. Sew the pocket bags to the seam allowance of the flap joining seam and to the seam allowance of the lower facing seam. Align the pocket bags, trim them, and stitch them together.

3. Sew the back princess seams and center back seam.
4. Sew the shoulder and side seams.
5. Place the front facings on the front pieces, right sides together, and pin along the front edges. Stitch the front edges. Sew the shoulder seams of the front facings and the back neckline facing.
6. Sew the center seam of the inner collar and press the seam allowances open. Finish the outer edge of the collar neatly. Sew the inner collar to the garment neckline and sew the outer collar to the facing neckline. Press the seam allowances open. Sew the pressed-open seam allowances of the inner collar and back neckline facing together from the inside.
7. Hem the garment.
8. Sew the sleeve seams, leaving the vents open in the elbow seams. Clip above the vent marks on the lower sleeve seam allowance. Press the seam allowances open above the vents. Turn up and sew the sleeve hems. Press the vent edges of the upper sleeve to the wrong side. Pin the vent and topstitch the vent edges over each other on the wrong side. Set the sleeves into the armholes, easing along the sleeve caps.
9. Sew in the shoulder pads.
10. Sew the darts in the front and back lining pieces and stitch the lining pieces together. Attach the lining to the sleeve hems, the inner edges of the front facings, and the back neckline facing. Finish the lining hem.
11. Make buttonholes on the right front and sew the buttons onto the left front.

Congratulations – your jacket are finished! :)