

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 5173 Classic Straight-Leg Trousers with Regular Waist

Recommendations on fabric: linen of 150 cm width.

You will also need: fusing; 1 zipper; 1 button.

### CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: 1 cm for all seams.

### Main fabric:

1. Front part – 2 pieces
2. Back part – 2 pieces
3. Back facing – 1 folded piece
4. Front facing – 2 pieces

Fusing: back/front facings

### INSTRUCTIONS:

1. Apply fusible interfacing to the wrong side of back and front facings.
2. Stitch darts and press the dart bulk toward the center.
3. Stitch side and inseam seams. Neaten seam allowances and press them open. Stitch the center front seam between the closure mark and the lower edge, and stitch the center back seam the same way.
4. Press the fly facing to the wrong side as follows: on the right edge, press it along the center front line; on the left side, stop pressing 1 cm before the center front line (this is the closure allowance). Stitch the zipper under the left zipper allowance so that the zipper teeth meet the fold. Pin the zipper opening edges together, matching the center front lines. Stitch the free zipper tape to the right fly facing, without catching the front fabric. Topstitch the right front piece along the closure line, catching the facing underneath.
5. Stitch the front and back facings together along the side edges. Press seam allowances open. Neaten the lower edge.
6. Place the facings on the upper edge of the pants, right sides together, and stitch. Turn right side out, secure the short edges, and topstitch the upper edge at 1 mm.
7. Press the hem to the wrong side, fold the edge under, and topstitch.
8. Make a buttonhole on the right side; sew a button on the left.

Congratulations – your trousers are finished! :)