

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5217 Jersey Dress with Draping and Slit

Recommendations on fabric: elastic fabric.

You will also need: zippe.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams 1 cm.

Main fabric:

1. Back center part – 2 pieces
2. Back side right part – 1 pieces
3. Back side left part – 1 pieces
4. Front side left part – 1 pieces
5. Outer stand-up collar – 1 pieces
6. Inner stand-up collar – 1 pieces
7. Front center part – 1 pieces
8. Front side right part – 1 pieces
9. Draping – 1 pieces
10. Sleeve – 2 pieces



INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. Sew the right front princess seam.
2. Fold the seam allowances of the upper and lower edges of the drape to the wrong side and sew. Form pleats according to the markings. Place the drape, wrong side down, on the right side of the center front piece and tack it along the edges.
3. Sew the center back seam downward from the marking. Sew the back princess seams and the left front princess seam, then sew the shoulder and side seams. Neaten the seams.
4. Form pleats in the upper stand collar. Place the outer and inner stand collars right sides together and stitch along the upper edge. Sew the lower edge of the outer stand collar to the garment neckline, right sides together. Fold under the lower edge of the inner stand collar and topstitch it to the joining seam.
5. Press the closure allowance toward the overlap side. Insert the zipper.
6. Form pleats along the sleeve caps. Trim the sleeve cap seam allowance to 1 cm. Sew the sleeve seams. Sew the sleeves into the armholes. Fold the hem allowances to the wrong side and stitch.
7. Press the slit allowances of the left front piece to the wrong side. Press all hem allowances to the wrong side and hand-stitch.

Congratulations – your dress are finished! :)