

If the pattern has a double line around it, the seam allowances are included.

**Note:** By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

**Important!** Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

## 5313 Coat

Recommendations on fabric: low nap faux fur.

You will also need: 6 hooks;  
lining

### CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



### Main fabric:

1. Back part – 1 detail
2. Front part – 2 details
3. Front band – 2 details
4. Inner collar – 1 detail
5. Outer collar trim – 1 detail
6. Outer collar – 1 detail
5. Upper sleeve – 2 details
6. Lower sleeve – 2 details

### Lining:

1. Back part – 1 detail
2. Front part - 2 details
3. Upper sleeve – 2 details
4. Lower sleeve – 2 details

#### INSTRUCTIONS:

1. Sew outer collar trim to the collar.
2. Fold the outer collar with inner one right sides together, then overstitch inner collar with outer one. Turn the collar right side out, then fit the edging from outer collar.
3. Sew bust dart into the front part.
4. Fold the drawstring lining stripe with fabric garment wrong side according to marking, turn out the lower end of the stripe. Tack the stripe with garment, then topstitch along marking.
5. Fold front band and front part right sides together, then overstitch along the edge, on the right side of front part upward to the notch marking ends of collar sewing-in. Sew front band lower edges to front part strictly along the marked line of hem folding-under. Turn edges right side out, then fit seams.
6. Sew shoulder seams. Sew side seams, with holes for string unsewn.
7. Sew the inner collar with the neckline, then sew inner collar to front bands.
8. Sew sleeve dart. Sew sleeve front seam.
9. Fold the drawstring lining stripe with fabric garment sleeve wrong side according to marking, turn out the lower end of the stripe. Tack the sides to garment sleeves, then topstitch along marking.
10. Sew edge sleeve seam, with the string hole unsewn.
11. Sew sleeves into armholes according to notches. Sew sleeve pads and sleeve heads into.
12. Mark hooks places on the wrong side. Make holes (with a special instrument) for hooks and eyes. Insert hooks (or eyes) into the holes; pull board pieces of 40-50 mm into hook rings (or eye). Sew hooks (or eyes) to front band through rings, then fix pulled into the hook ends of the board.

13. Sew lining sleeve seams, then sew the sleeves into. Oversew lining seams, hem upward the waist. Press the lining. Sew the lining to front band and outer collar inner edges. Sew collar joining seam allowances. Turn lining sleeves under and sew to garment hem turning-under, turn the extra lining into the wrong side and press. Turn the coat right side out through unsewn hem. Cut the hem, then turn it under and topstitch, so that the lining was 1 cm shorter than the fabric garment. Turn the hem and sew by hand.

14. Trim the string into the drawstring. Gather the fabric with ties, then trim the gathering, gather ends of the string.

Congratulations, your coat is ready! :)