

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5495 Women's Shirt with Slits

Recommendations on fabric: .

You will also need: .

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.



Seam allowances: 1 cm for all seams.

Main fabric:

1. Back part – 1 piece
2. Front part – 2 pieces
3. Collar – 2 pieces
4. Stand-up collar – 2 pieces
5. Cuff – 2 pieces
6. Sleeve – 2 pieces
7. Front band – 2 piece

Fusing: front band, outer collar, stand-up collar, cuff

INSTRUCTIONS:

1. Apply fusible interfacing to the wrong side of the front band, outer collar, stand-up collar, and cuffs.
2. Sew front darts. Sew back darts. Sew back waist darts. Press all darts toward the center.
3. Neaten the inner edge of the front band.
4. Sew the front edges with front bands, trim corners, and turn the front bands right side out. Press the edges.
5. Sew shoulder and side seams. Neaten and press them toward the back. Secure front bands with a 1 cm stitch at the shoulder seams.
6. Neaten sleeve edges. Sew the sleeve seam up to the notch, press seam allowances open. Press the slit and sew a decorative stitch at 0.5 cm from the edge.
7. Set in the sleeves.
8. Stitch the inner collar to the outer collar, turn the collar right side out, and press.
9. Sew the stand collars together, inserting the collar between them. Press the stand-up collar.
10. Sew the inner stand-up with collar to the neckline. Fold the outer stand-up's open edge under and topstitch along the seam that joins the inner stand-up.
11. Neaten the side edges of the cuff and turn it right side out. Press the finished cuff.
12. Sew the outer cuff to the lower edge of the sleeve. Fold the inner cuff under and topstitch. Make buttonholes on the cuff and sew on buttons.
13. Neaten the garment hem, fold it under, and topstitch.
14. Make buttonholes on the right front, sew buttons on the left front.

Congratulations, your shirt is ready! :)