If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.
Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.
Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5806 Dress with Wrap Effect and Collar



Recommendations on fabric: light to mid-weight stretch-knit fabric.

You will also need: fusible interfacing.

CUTTING:
The word, “beam” used on some patterns means “straight of grain”. Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm. On hem and hem of sleeve – 2 cm, on front part neckline edge from notch up to hem – 1. 5 cm.

Main fabric:
1. Bodice back – cut 2
2. Skirt back – cut 1 on fold
3. Bodice front – cut 2
4. Skirt front – cut 1 on fold
5. Collar – cut 2
6. Belt – cut 1
7. Sleeve – cut 2

INSTRUCTIONS:
Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save

elasticity.

1. Apply fusible interfacing to the outer collar.

2. Form and sew the pleats on the front bodice pieces according to the pattern markings. Clip the seam allowance near the marked notch on the neckline. Serge the front edges from the notch to the lower edge of the bodice. Fold the seam allowances to the wrong side and topstitch.

3. Sew the center back bodice seam. Serge the seam allowances and press them toward the left.

4. Sew the shoulder seams. Serge the seam allowances and press them toward the back.

5. Pin the collar pieces together, right sides facing, and sew along the ends and outer edge, beginning and ending the stitching exactly at the marked collar attachment seam lines. Turn the collar right side out, shape the edges, and press. Sew the outer collar to the neckline. Fold under the seam allowance of the inner collar and secure it by stitching in the ditch along the outer collar attachment seam.

6. Sew the back skirt to the back bodice. Serge the seam allowances and press them upward toward the bodice.

7. Overlap the right front bodice over the left, aligning the pleats and pattern markings, and baste the layers together. Sew the front skirt to the front bodice. Serge the seam allowances and press them upward toward the bodice.

8. Sew the side seams. Serge the seam allowances and press them toward the back.

9. Sew the sleeve seams. Serge the seam allowances and press. Sew gathering stitches along the sleeve caps to adjust the ease.

10. Set the sleeves into the armholes, matching the notches and distributing the ease evenly. Serge the seam allowances and press.

11. Serge the lower edge of the dress and the lower sleeve edges. Fold the hem allowances to the wrong side, press, and topstitch.

12. Fold the belt in half lengthwise, right sides together, and sew around the edges, leaving a 15 cm opening along the long edge for turning. Turn the belt right side out, shape the edges, and press. Close the opening with slip stitches. Attach the belt to the left side seam of the dress.

Congratulations – your dress are finished! :)