

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

5835 Double-breasted jacket with stand-up collar

Recommendations on fabric: fabric suitable for coats approx. 2 m (size 32-42), approx. 2.4 m (size 44-54) with a fabric width of 150 cm.

Lining approx. 1.5 m (size 32-42), approx. 2 m (size 44-54) with a fabric width of 150 cm.



You will also need: fusible interfacing, 13 buttons (minimum 2 cm in diameter), shoulder pads, and sleeve heads

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowance: 1 cm for all seams; 3 cm for the garment hem

Main fabric:

1. Center upper back – 2 pieces
2. Side upper back – 2 pieces
3. Lower back – 1 piece
4. Side upper front – 2 pieces
5. Side lower front – 2 pieces
6. Center front – 2 pieces

7. Upper sleeve – 2 pieces
8. Lower sleeve – 2 pieces
9. Stand-up collar – 2 pieces
10. Front band facing – 2 pieces
11. Flap – 4 pieces
12. Cuff – 2 pieces
13. Strap – 2 pieces
14. Back neck facing – 1 piece
15. Shoulder strap – 2 pieces
16. Loop – 1 piece
17. Decorative button loop – 3 pieces

Lining:

1. Upper back – 2 pieces
2. Lower back – 1 piece
3. Front – 1 piece
4. Upper sleeve – 2 pieces
5. Lower sleeve – 2 pieces
6. Pocket bag – 4 pieces

Fusible interfacing:

1. Center front – 2 pieces
2. Stand-up collar – 1 piece
3. Front band facing – 2 pieces
4. Flap – 2 pieces
5. Cuff – 2 pieces
6. Strap – 2 pieces
7. Back neck facing – 1 piece
8. Shoulder strap – 2 pieces

INSTRUCTIONS:

1. Apply fusible interfacing to the wrong side of the listed pieces.
2. Pin the flap, right sides together, and sew the outer edge. Trim corners, turn right side out, and press. Make a decorative stitch 0.7 cm from the edge. Sew pocket bags to the flap.
3. Sew the side upper front and lower front right sides together. Press the seam apart and topstitch 0.7 cm from the seam.
4. Pin the pocket bag to the right side of the side front. Pin the flap with the attached

pocket bag to the center front, matching notches, right side down. Sew the pocket bag to the pocket entrance seam allowance. Turn up the side front seam and topstitch it onto the pocket bag.

5. Sew the side front and pocket bag to the center front. Slash seam allowances at the pocket entrance ends, press curved seam allowances toward the center, and press the pocket at the same time. Make a decorative stitch 0.7 cm along the curved seam up to the waist.
6. Sew the back center seam, press seam allowance to the left, and topstitch 0.7 cm from the seam. Sew the side backs to the center back, press seam allowances toward the center, and topstitch 0.7 cm from the seam. Sew the lower back to the upper back, press seam allowances apart, and topstitch 0.7 cm from the seam.
7. Sew the shoulder and side seams. Press seam allowances apart.
8. Sew the back neck facing to the front band facings. Press seam allowances apart.
9. Sew the outer collar to the garment neckline. Sew the inner collar to the facing. Clip curves and press seams apart. Pin the facing to the garment, right sides together, and sew along the center front edges and stand-up collar in one seam. Trim corners, turn, and press.
10. Fold the strap lengthwise, right sides together, and sew along the long and curved edges. Trim corners, turn right side out, and press. Make a decorative stitch 0.7 cm from the edge. Whipstitch the buttonhole.
11. Sew the front sleeve seam and press seam allowances apart.
12. Press the cuff half lengthwise, right side out. Sew the outer edge of the cuff to the lower edge of the sleeve. Press the seam toward the cuff and topstitch 0.7 cm from the seam. Sew the sleeve elbow seam, inserting the strap into the seam.
13. Make a gathering stitch along the sleeve cap for ease. Sew the sleeve into the armhole, matching notches and adjusting ease.
14. Pin the shoulder straps right sides together and sew around the long and curved edges. Trim corners, turn right side out, and press. Make a decorative stitch 0.7 cm along the edge. Whipstitch the buttonhole and serge the open edge.
15. Fold the button loops three times lengthwise and sew with a flatlock stitch. Cut it in two and serge the edges.

16. Sew the loop and shoulder strap to the shoulder as indicated in the technical drawing.

17. Sew in shoulder pads and sleeve heads.

18. Sew the lining in the same manner as the main fabric, leaving an opening in the right sleeve seam for turning. Pin the lining and garment right sides together and sew to the inner edges of the facing. Press the stand-up collar seam apart. Stitch in seam allowances and pin close to the seams. Sew horizontally across the lower front band facing, trim corners, and press. Sew lining to hem. Sew sleeve lining to the inner cuff. Turn the garment right side out through the opening in the right sleeve seam and close the opening.

19. Fold the decorative button loops three times lengthwise and stitch with a flatlock stitch. Adjust the loop length, serge the edges, and whipstitch the buttonhole.

20. Sew buttons on the garment, aligning them with the button loops.

Congratulations, your jacket is ready! :)