

If the pattern has a double line around it, the seam allowances are included.

Note: By default, seam allowances are NOT included (single line) and will need to be added when laying out and cutting details.

Seam Allowance: 1 cm on all seams; hem guidelines are printed on pattern.

Important! Please print all the paper patterns and lay them out at the width of fabric you plan to use (usually from 90 to 150 cm) to see how much fabric you will need.

Don't forget to take into account pieces to be duplicated or cut on a fold. When sewing the garment, pay attention to notches. They must match up with corresponding pieces.

2677 T-shirt with Yoke and V-Neck

Recommendations on fabric: soft natural/mixed knit fabric of medium stretchiness.

You will also need: knit fusible interfacing.

CUTTING:

The word, "beam" used on some patterns means "straight of grain". Some pieces will be cut on the fold, this is noted on the pattern piece. Mark all notches and other design features such as darts, pleats etc. from the pattern onto your fabric.

Seam allowances: all seams – 1 cm; seam allowance along the hem of garment and hem of sleeve – 2 cm.

Main fabric:

1. Back – cut 1 on fold
2. Front – cut 1 on fold
3. Yoke – cut 2
4. Placket – cut 2
5. Sleeve – cut 2
6. Back neck facing – cut 1

Fusible interfacing:



1. Placket – cut 2
2. Back neck facing – cut 1

INSTRUCTIONS:

Advice: sew knit pieces with special elastic/zig-zag stitches. If you use an overlock, cut seam allowances to 0.6-0.8 cm width. Topstitch hem allowances with double needle to save elasticity.

1. Fold the plackets in half lengthwise, wrong sides together. Place the corner of the right placket over the corner of the left placket and baste the pieces together along the lower edge.
2. Fold the yoke in half lengthwise, wrong sides together, and press the fold. Baste the yoke layers together along the armhole edges.
3. Sew the yokes to the front, inserting the plackets and clipping into the seam allowance near the corner. Serge the seam allowances and press them downward. Sew a decorative topstitch 0.5 cm from the seam.
4. Serge the outer edge of the back neckline facing. Pin the neckline facing to the back and sew the neckline exactly to the marked shoulder seam line. Clip the seam allowances, turn the facing to the wrong side, and press.
5. Sew the shoulder seams, placing the front between the back and the facing. Press the seam allowances toward the back and serge.
6. Sew the side seams. Press the seam allowances toward the back and serge.
7. Sew the sleeve seams. Press the seam allowances toward the back and serge. Set the sleeves into the armholes, matching the notches. Serge the seam allowances and press.
8. Serge the garment hem and sleeve hem allowances. Fold them to the wrong side and topstitch.

Congratulations – your t-shirt are finished! :)